Assignment 7 – Introduction to Packed Decimal (75 points)

This program is a rather simple introduction to packed decimal and packed decimal arithmetic.

First, copy the following Assembler program into a new member of your ASSIGNS PDSE named ASSIGN7.

Be sure the program is surrounded by the correct JCL:

```
PRINT NOGEN
*********************
*
  CSCI 360
                       ASSIGNMENT 7
                                              SUMMER 2021
*
*
*
*********************
PAYROLL CSECT
  STANDARD ENTRY LINKAGE ESTABLISHING R12 AS BASE REGISTER
        STM
             14,12,12(13) SAVE REGS IN CALLER'S SAVE AREA
        LR
             12,15
                          COPY CSECT ADDR INTO R12
                          ESTABLISH R12 AS THE BASE REG
        USING PAYROLL,12
             14,REGSAVE
        LA
                          R14 POINTS TO THIS CSECT'S SAVE AREA
        ST
             14,8(,13)
                          STORE ADDR OF THIS CSECT'S SAVE AREA
        ST
             13,4(,14)
                          STORE ADDR OF CALLER'S SAVE AREA
                          POINT R13 AT THIS CSECT'S SAVE AREA
        LR
             13,14
*
*
  Here is where you will write your program.
*
  STANDARD EXIT LINKAGE WITH RC OF 0 RETURNED IN R15
*
        SR
              15,15
                          R15 = RETURN CODE OF 0
        L
             13,4(,13)
                          POINT R13 TO CALLER'S SAVE AREA
             14,12(,13)
        L
                         RESTORE REGISTER 14
        LM
             0,12,20(13) RESTORE R0 THRU R12
        BR
             14
                          RETURN TO CALLER
        LTORG
* THE FOLLOWING TWO LINES PUTS A LABEL ON YOUR STORAGE ON A
* 32-BYTE BOUNDARY SO THAT YOU CAN FIND IT EASILY IN A DUMP
        ORG
             PAYROLL3+((*-PAYROLL3+31)/32)*32
        DC
             C'* PROGRAM STORAGE FOR PAYROLL3 *'
```

REGSAVE DS 18F PROGRAM'S REGISTER SAVE AREA

*

END PAYROLL

You will write your source code in between the lines of standard entry and exit linkage code. Of course, you can add variables and other storage declarations immediately following the LTORG provided but place them above the 18-fullword caller's register storage area.

Secondly, change the input data member to:

```
//FT05F001 DD DSN=KC02322.CSCI360.DATASU21(DATA7),DISP=SHR
```

To assist you, here is the data in the DATA7 member:

WOLFGANG AMADEUS MOZART	1234515802550
RICHARD STRAUSS	2345619800001
AMY BEACH	2213210803120
DAME ETHEL SMYTHE	6546522801590
PETER ILYICH TCHAIKOVSKY	4456023283407
ANTON BRUCKNER	9987022802100
LUDWIG VAN BEETHOVEN	1334515802550
JOHANNES BRAHMS	2445619800001
BELA BARTOK	2253210803120
MAX REGER	1146522801590
SAMUEL BARBER	1336023283407
GIUSEPPE VERDI	9987322802100
JOHANN SEBASTIAN BACH	1234215802550
JOSEPH HAYDN	2345219800001
GEORG FRIEDRICH HANDEL	2213110803120
NIKOLAI RIMSKY-KORSAKOV	4437823283407
EDWARD ELGAR	6541122801590
CLAUDE DEBUSSY	9985522802100
ANTONIN DVORAK	1334615802550
THOMAS TALLIS	2445719800001
RALPH VAUGHAN WILLIAMS	2253810803120
RICHARD WAGNER	1147722801590
FREDERIC CHOPIN	1777723283407
JOAN TOWER	9921122802100

Each of the above input records has the following layout:

Data Field	Data Type	Columns	Max. Value
Employee Name	Alphanumeric	1-25	
Employee ID	Alphanumeric	26-30	
Hourly Pay Rate	Zoned Decimal	31-34	\$99.99 (two implied decimal places)
Hours Worked	Zoned Decimal	35-38	99.99 (two implied decimal places)
Unused		39-80	

As before, read the employee records one at a time using a standard read loop and printing a detail line for each employee so that your output looks like that provided to you in the Assignment 7 folder on Blackboard.

For each employee, move their name to the print line and move their ID to the print line. Make sure your read loop works at this point before moving on.

Next, using only packed decimal instructions, PACK and ED the Hourly Pay Rate into the print line showing the decimal point. Do the same for the Hours Worked.

Finally, calculate the gross pay amount using MP, round it to two decimal places and ED it into the print line showing the decimal point.

The only packed decimal instructions you will need are: PACK, ED, ZAP, MP and SRP.

You will no longer need to use XDECI or XDECO. DO NOT use them!

Name your detail line you print for each employee DETAIL and place the following two lines at the top of your read loop:

```
MVI DETAIL+1,C''
MVC DETAIL+2(131),DETAIL+1
```

These two lines set all but the very first byte – the carriage control character – of your 133-byte detail line to spaces to prepare for the next employee information.

Submit your ASSIGN7.txt file on Blackboard as before.