Remediation delle vulnerabilità

Vulnerabilita risolte:

Bind Shell Backdoor Detection
NFS Exported Share Information Disclosure
VNC server 'password" Password

1.Bind Shell Backdoor Detection

Per quanto riguarda la risoluzione di questa vulnerabilità, ho abilitato il firewall di Mestasploitable con il comando "UFW ENABLE"

Dopodichè, ho detto al firewall di acconsentire a tutte le regole di default con "UFW DEFAULT ALLOW*

Clone di metaesploit2 [In esecuzione] - Oracle VM VirtualBox

File Macchina Visualizza Inserimento Dispositivi Aiuto

```
                              [ Wrote 12 lines ]

msfadmin@metasploitable:~$ ufw enable
ERROR: You need to be root to run this script
msfadmin@metasploitable:~$ sudo su
root@metasploitable:/home/msfadmin# ufw enable
Firewall started and enabled on system startup
root@metasploitable:/home/msfadmin# ufw default allow
Default policy changed to 'allow'
(be sure to update your rules accordingly)
root@metasploitable:/home/msfadmin# ufw deny 1524
Rule added
root@metasploitable:/home/msfadmin# ufw status
Firewall loaded

To                         Action  From
--                         ------  ----
1524:tcp                   DENY    Anywhere
1524:udp                   DENY    Anywhere

root@metasploitable:/home/msfadmin# _
```

Integrazione del mouse...

Acquisizione automatica della tastiera...

CTRL (DESTRA)

2. NFS Exported Share Information Disclosures

Per quanto riguarda la prima vulnerabilità, la remediation da applicare e quella di inserire all'interno della sottocartella del root /etc.

La prima cosa da fare è quella di visualizzare all'interno delle sottocartelle del root con "ls -a".

Cerchiamo la directory "/etc" e apriamo il file "exports".

All'interno di questo file, andremo a modificare 1'* in fondo alla pagina con l'ip della nostra macchina.

Una volta fatto, riavviamo la macchina.

Clone di metaesploit2 [In esecuzione] - Oracle VM VirtualBox

File Macchina Visualizza Inserimento Dispositivi Aiuto

```
  GNU nano 2.0.7             File: /etc/exports

# /etc/exports: the access control list for filesystems which may be exported
#               to NFS clients.  See exports(5).
#
# Example for NFSv2 and NFSv3:
# /srv/homes       hostname1(rw,sync) hostname2(ro,sync)
#
# Example for NFSv4:
# /srv/nfs4        gss/krb5i(rw,sync,fsid=0,crossmnt)
# /srv/nfs4/homes  gss/krb5i(rw,sync)
#

/mnt/newdisk    192.168.80.101(rw,sync,no_root_squash,no_subtree_check)

                              [ Wrote 12 lines ]

msfadmin@metasploitable:~$ _
```

Integrazione del mouse...

Acquisizione automatica della tastiera...

CTRL (DESTRA)

3. VNC Server 'password' Password

Per modificare la password del VNC Server, troviamo all'interno della directory msfadmin, con il comando ls-a, il directory .vne. All'intemo di questa directory, andremo a eseguire il comando "vnopasswd" per cambiare la password.

Alla fine riavviamo la macchina.

Clone di metaesploit2 [In esecuzione] - Oracle VM VirtualBox

File Macchina Visualizza Inserimento Dispositivi Aiuto

```
msfadmin@metasploitable:~$ ls -a
.               .distcc   .gconfd         .rhosts                    .vnc
..              .fluxbox  .mysql_history  .ssh                       vulnerable
.bash_history   .gconf    .profile        .sudo_as_admin_successful  .Xauthority
msfadmin@metasploitable:~$ cd .vnc
msfadmin@metasploitable:~/.vnc$ vncpassword
-bash: vncpassword: command not found
msfadmin@metasploitable:~/.vnc$ vncpasswd
Using password file /home/msfadmin/.vnc/passwd
Password:
Warning: password truncated to the length of 8.
Verify:
Passwords do not match. Please try again.

Password:
Verify:
Would you like to enter a view-only password (y/n)? y
Password:
Verify:
msfadmin@metasploitable:~/.vnc$ -_
```

Integrazione del mouse...

Acquisizione automatica della tastiera...

CTRL (DESTRA)