

Router>enable Router#config t Enter configuration commands, one per line. End with CNTL/Z. Router(config) #interface Fa0/0 Router(config-if) #ip address 10.0.0.1 255.0.0.0 Router (config-if) #no shutdown Router (config-if) # %LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up %LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up Router (config-if) #exit Router(config) #interface Se2/0 Router(config-if) #ip address 20.0.0.1 255.0.0.0 Router (config-if) #encapsulation ppp Router(config-if) #clock rate 64000 Router (config-if) #no shutdown %LINK-5-CHANGED: Interface Serial2/0, changed state to down

Router (config-if) #exit

```
louter#config t
Inter configuration commands, one per line. End with CNTL/Z.
Router (config) #router ospf 1
louter(config-router) #router-id 3.3.3.3
louter(config-router) #network 40.0.0.0 0.255.255.255 area 2
louter(config-router) #network 30.0.0.0 0.255.255.255 area 0
louter(config-router) #end
Router#
SYS-5-CONFIG_I: Configured from console by console
00:26:19: %OSPF-5-ADJCHG: Process 1, Nbr 2.2.2.2 on Serial3/0 from LOADING to FULL, Loading Done
louter#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
      D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
      N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
      El - OSPF external type 1, E2 - OSPF external type 2, E - EGP i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
      * - candidate default, U - per-user static route, o - ODR
      P - periodic downloaded static route
Sateway of last resort is not set
) IA 20.0.0.0/8 [110/128] via 30.0.0.1, 00:02:45, Serial3/0
    30.0.0.0/8 is variably subnetted, 2 subnets, 2 masks
       30.0.0.0/8 is directly connected, Serial3/0
       30.0.0.1/32 is directly connected, Serial3/0
   40.0.0.0/8 is directly connected, FastEthernet0/0
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router (config) #
01:11:01: %OSPF-4-ERRRCV: Received invalid packet: mismatch area ID, from
backbone area must be virtual-link but not found from 20.0.0.2, Serial2/0
01:11:11: %OSPF-4-ERRRCV: Received invalid packet: mismatch area ID, from
backbone area must be virtual-link but not found from 20.0.0.2, Serial2/0
Router (config) #route
01:11:21: %OSPF-4-ERRRCV: Received invalid packet: mismatch area ID, from
backbone area must be virtual-link but not found from 20.0.0.2, Serial2/0
r ospf 1
```

01:11:31: %OSPF-4-ERRRCV: Received invalid packet: mismatch area ID, from backbone area must be virtual-link but not found from 20.0.0.2, Serial2/0

01:11:41: %OSPF-4-ERRRCV: Received invalid packet: mismatch area ID, from backbone area must be virtual-link but not found from 20.0.0.2, Serial2/0

01:11:56: %OSPF-5-ADJCHG: Process 1, Nbr 1.1.1.1 on OSPF_VL0 from LOADING to

Router(config-router) #

irtual-link 1.1.1.1
Router(config-router)#

Router(config-router) #area 1 v