## Nu Html Checker

This tool is an ongoing experiment in better HTML checking, and its behavior remains subject to change

## Showing results for services.jsx

Checker Input
Show source outline image report Options
Check by file upload ➤ Choisir un fichier Aucun fichier choisi
Uploaded files with .xhtml or .xht extensions are parsed using the XML parser.
Check

Use the Message Filtering button below to hide/show particular messages, and to see total counts of errors and warnings.

Message Filtering

1. Warning Consider adding a lang attribute to the html start tag to declare the language of this document.
From line 1, column 1; to line 1, column 26
import React from "react"; ∴ impor
For further guidance, consult Declaring the overall language of a page and Choosing language tags.

If the HTML checker has misidentified the language of this document, please <u>file an issue report</u> or <u>send e-mail to report the problem</u>.

- 2. Error The character encoding was not declared. Proceeding using windows-
- 3. Error Non-space characters found without seeing a doctype first. Expected <!DOCTYPE html>.

  From line 1, column 1; to line 1, column 26

  import React from "react"; wimpor
- 4. Error Element head is missing a required instance of child element title.

  From line 1, column 1; to line 1, column 26

  import React from "react"; ← impor

  Content model for element head:

  If the document is an iframe srcdoc document or if title information is available from a higher-

https://validator.w3.org/nu/#file 1/5

level protocol: Zero or more elements of metadata content, of which no more than one is a title

element and no more than one is a base element.

Otherwise: One or more elements of <u>metadata content</u>, of which exactly one is a <u>title</u> element and no more than one is a <u>base</u> element.

5. Error Self-closing syntax ( /> ) used on a non-void HTML element. Ignoring the slash and treating as a start tag.

From line 9, column 13; to line 9, column 22 ≺Header />↔

6. Error The main element must not appear as a descendant of the header element.

From line 10, column 13; to line 10, column 18 ⟨main⟩←

7. Error Attribute classname not allowed on element img at this point.

From line 11, column 17; to line 15, column 18

<img $\leftrightarrow$ <src="../../img/banner.jpg" $\leftrightarrow$ alt="img du fond" $\leftrightarrow$ className="img-fluid" $\leftrightarrow$  $/>\leftrightarrow$ 

Attributes for element img:

Global attributes

<u>alt</u> — Replacement text for use when images are not available

src — Address of the resource

srcset — Images to use in different situations, e.g., high-resolution displays, small monitors, etc.

sizes — Image sizes for different page layouts

crossorigin — How the element handles crossorigin requests

usemap — Name of image map to use

<u>ismap</u> — Whether the image is a server-side image map

width — Horizontal dimension

**<u>height</u>** — Vertical dimension

<u>referrer policy</u> — <u>Referrer policy</u> for <u>fetches</u> initiated by the element

<u>decoding</u> — Decoding hint to use when processing this image for presentation

loading — Used when determining loading deferral

<u>fetchpriority</u> — Sets the <u>priority</u> for <u>fetches</u> initiated by the element

8. Info Trailing slash on void elements has no effect and interacts badly with unquoted attribute values.

From line 11, column 17; to line 15, column 18

https://validator.w3.org/nu/#file 2/5


```
<img←
                                            src="../../img/banner.jpg"

     alt="img du fond"↔
                                               className="img-fluid"↔
                                                                                         />↩
 9.
     Error Attribute classname not allowed on element div at this point.
     From line 16, column 17; to line 16, column 49
                <div className="container-fluid">←
     Attributes for element div:
        Global attributes
     Error Attribute classname not allowed on element div at this point.
10.
     From line 17, column 21; to line 17, column 41
                <div className="row">↔
     Attributes for element div:
        Global attributes
     Error Attribute classname not allowed on element div at this point.
11.
     From line 18, column 25; to line 18, column 59
                <div className="col-12 titleOffer">←
     Attributes for element div:
        Global attributes
12.
     Error Attribute classname not allowed on element section at this point.
     From line 22, column 25; to line 22, column 59
                <section className="row box-offer">←
     Attributes for element section:
        Global attributes
     Error Attribute classname not allowed on element article at this point.
13.
     From line 23, column 29; to line 23, column 82
                <article className="col-12 col-md-4 col-lg-4 service">←
     Attributes for element <u>article</u>:
        Global attributes
     Error Attribute classname not allowed on element i at this point.
14.
     From line 24, column 33; to line 24, column 77
                <i className="fa-solid fa-display iconOffer"></i>
     Attributes for element i:
        Global attributes
```

https://validator.w3.org/nu/#file 3/5

```
15.
     Error Attribute classname not allowed on element article at this point.
     From line 32, column 29; to line 32, column 82
                <article className="col-12 col-md-4 col-lg-4 service">←
     Attributes for element article:
        Global attributes
     Error Attribute classname not allowed on element i at this point.
16.
     From line 33, column 33; to line 33, column 79
                <i className="fa-solid fa-file-code iconOffer"></i>
     Attributes for element i:
        Global attributes
      Error Attribute classname not allowed on element article at this point.
17.
     From line 40, column 29; to line 40, column 82
                <article className="col-12 col-md-4 col-lg-4 service">←
     Attributes for element article:
        Global attributes
18.
     Error Attribute classname not allowed on element | i | at this point.
     From line 41, column 33; to line 41, column 93
                <i className="fa-solid fa-magnifying-glass-dollar iconOffer"></i></i>
     Attributes for element i:
        Global attributes
     Warning | Section lacks heading. Consider using | h2 | h6 | elements to add
19.
     identifying headings to all sections, or else use a | div| element instead for any
     cases where no heading is needed.
     From line 22, column 25; to line 22, column 59
                <section className="row box-offer">↔
     Error The element footer must not appear as a descendant of the header
20.
     element.
     From line 54, column 13; to line 54, column 22
                <Footer />←
     Error Self-closing syntax ( /> ) used on a non-void HTML element. Ignoring the
21.
     slash and treating as a start tag.
     From line 54, column 13; to line 54, column 22
```

https://validator.w3.org/nu/#file 4/5



Document checking completed.

Used the HTML parser.

Total execution time 5 milliseconds.

About this checker • Report an issue • Version: 24.8.2

https://validator.w3.org/nu/#file 5/5