Extended Addition and Subtraction

The ADC (add with carry) instruction in assembly language is used to add two operands, taking into account the Carry flag.

The Carry flag is set when the result of a previous addition or subtraction operation overflows.

The ADC instruction is typically used to perform multi-byte or multiword addition and subtraction operations.

After the first instruction, the AL register contains the value FEh and the Carry flag is set.

The second instruction then adds the Carry flag to the DL register, resulting in a final value of 01FEh in the DL:AL register pair.

Here is another example of using the ADC instruction:

```
into the EAX register
into the EAX regi
```

After the first instruction, the EAX register contains the value FFFFFFFh and the Carry flag is set.

The second instruction then adds the Carry flag to the EDX register, resulting in a final value of 00000001FFFFFFFEh in the EDX:EAX register pair.

The ADC instruction can be used to add operands of any size, including 1024-bit integers.

To do this, multiple ADC instructions would be used in sequence, carrying the Carry flag from one instruction to the next.

Here is an example of how to add two 1024-bit integers using the ADC instruction:

```
1000; Load the first operand into the [EAX:EBX:ECX:EDX] register quad
1001 mov eax, [operand1]
1002 mov ebx, [operand1 + 4]
1003 mov ecx, [operand1 + 8]
1004 mov edx, [operand1 + 12]
1005
1006; Load the second operand into the [ESI:EDI:ESI:EDI] register quad
1007 mov esi, [operand2]
1008 mov edi, [operand2 + 4]
1009
1010; Add the two operands, carrying the Carry flag from each instruction to the next
1011 adc eax, esi
1012 adc ebx, edi
1013 adc ecx, edi
1014 adc edx, esi
1015
1016 ; Save the result in the [EAX:EBX:ECX:EDX] register quad
1017 mov [result], eax
1018 mov [result + 4], ebx
1019 mov [result + 8], ecx
1020 mov [result + 12], edx
```

This code will add the two 1024-bit operands stored in the operand1 and operand2 arrays and store the result in the result array. Let's break down the code step by step:

Loading the First Operand (operand1):

The code begins by loading the first operand, which is a 1024-bit value, into the [EAX:EBX:ECX:EDX] register quad. It does this in four 32-bit chunks (4 * 32 = 128 bits):

mov eax, [operand1]: Loads the first 32 bits of operand1 into the EAX register.

mov ebx, [operand1 + 4]: Loads the next 32 bits (bits 32-63) of

operand1 into the EBX register.

mov ecx, [operand1 + 8]: Loads the following 32 bits (bits 64-95) of operand1 into the ECX register.

mov edx, [operand1 + 12]: Loads the last 32 bits (bits 96-127) of
operand1 into the EDX register. Loading the Second Operand
(operand2):

The code then loads the second operand, which is also a 1024-bit value, into the [ESI:EDI:ESI:EDI] register quad. Like the first operand, it does this in four 32-bit chunks:

mov esi, [operand2]: Loads the first 32 bits of operand2 into the ESI register.

mov edi, [operand2 + 4]: Loads the next 32 bits (bits 32-63) of operand2 into the EDI register.

Adding the Two Operands with Carry Propagation:

The actual addition of the two operands is performed in this step. It uses the adc (add with carry) instruction, which allows for carry propagation.

adc eax, esi: Adds the first 32 bits of the first operand (EAX) and the first 32 bits of the second operand (ESI) along with any carry from the previous addition. The result is stored in EAX.

adc ebx, edi: Adds the next 32 bits of the first operand (EBX) and the next 32 bits of the second operand (EDI) along with any carry from the previous addition. The result is stored in EBX.

adc ecx, edi: Adds the following 32 bits of the first operand (ECX) and the next 32 bits of the second operand (EDI) along with any carry from the previous addition. The result is stored in ECX.

adc edx, esi: Adds the last 32 bits of the first operand (EDX) and the first 32 bits of the second operand (ESI) along with any carry from the previous addition. The result is stored in EDX.

Storing the Result in the result Array:

Finally, the result of the addition is saved back into the result array in four 32-bit chunks.

mov [result], eax: Stores the first 32 bits of the result (in EAX) in the result array.

mov [result + 4], ebx: Stores the next 32 bits (in EBX) of the result
in the result array.

mov [result + 8], ecx: Stores the following 32 bits (in ECX) of the
result in the result array.

mov [result + 12], edx: Stores the last 32 bits (in EDX) of the
result in the result array.

This code essentially performs a multi-precision addition for 1024bit operands, taking care of carry propagation between 32-bit chunks. It's a low-level operation that handles large integers by breaking them into manageable pieces.

The ADC instruction is a powerful tool for performing multi-byte and multi-word addition and subtraction operations. It can be used to add and subtract operands of any size, including very large integers.

The Extended_Add procedure below is an example of how to add two extended integers of the same size using assembly language.

It works by iterating through the two integers, adding each corresponding byte and carrying over any carry from the previous iteration. The procedure takes four arguments:

ESI and **EDI**: Pointers to the two integers to be added.

EBX: A pointer to a buffer in which the sum will be stored. The buffer must be one byte longer than the two integers.

ECX: The length of the longest integer in bytes. The procedure assumes that the integers are stored in little-endian order, with the least significant byte at the lowest offset.

Here is a more detailed explanation of the code:

```
1025 ;-----
1026 ;Extended_Add PROC
1027 ;-----
1028 pushad; Save all registers on the stack.
1029 clc; Clear the Carry flag.
1031 L1: mov al,[esi]; Get the next byte from the first integer.
1032; Add the next byte from the second integer, including any carry from the previous iteration.
1033 adc al,[edi]
1034 pushfd; Save the Carry flag.
1035 mov [ebx],al; Store the partial sum.
1036 add esi,1; Advance the pointers to the next bytes in the integers.
1037 add edi,1
1038 add ebx,1
1039 popfd; Restore the Carry flag.
1040 loop L1; Repeat the loop until all bytes have been added.
1042; Clear the high byte of the sum, since it may contain a carry.
1043 mov byte ptr [ebx],0
1044 adc byte ptr [ebx],0; Add any leftover carry.
1046 popad; Restore all registers from the stack.
1047 ret; Return from the procedure.
1048 Extended_Add ENDP
```

The loop at L1 iterates through the two integers, adding each corresponding byte and carrying over any carry from the previous iteration.

The Carry flag is saved and restored on each iteration so that it is always in the correct state when the next addition is performed.

After the loop has finished iterating, the high byte of the sum is cleared.

This is necessary because the high byte may contain a carry from the addition of the two highest bytes of the integers.

The ADC instruction is then used to add any leftover carry to the high byte of the sum.

Finally, the registers are restored from the stack and the procedure returns.

The Extended_Add procedure is a useful example of how to perform extended precision arithmetic in assembly language.

It can be used to add two integers of any size, regardless of whether they fit within the registers of the CPU.

The following sample code calls the Extended_Add procedure to add two 8-byte integers:

```
1053 .data
         op1 BYTE 34h, 12h, 98h, 74h, 06h, 0A4h, 0B2h, 0A2h
1054
         op2 BYTE 02h, 45h, 23h, 00h, 00h, 87h, 10h, 80h
1055
         sum BYTE 9 dup(0)
1056
1057
1058 .code
1059 main PROC
         ; Load addresses of operands and result
1060
         mov esi, OFFSET op1    ; First operand
1061
         mov edi, OFFSET op2 ; Second operand
1062
         mov ebx, OFFSET sum ; Result operand
1063
1064
1065
         ; Determine the number of bytes to process
         mov ecx, LENGTHOF op1
1066
1067
         ; Call the Extended Add function
1068
         call Extended Add
1069
1070
         ; Display the sum.
1071
         mov esi, OFFSET sum
1072
1073
         mov ecx, LENGTHOF sum
         call Display Sum
1074
1075
         ; Call a function to output a newline.
1076
1077
         call Crlf
1078
1079
         ; Exit the program
         invoke ExitProcess, 0
1080
1081
1082 main ENDP
```

The .data section of the code defines three byte arrays: op1, op2, and sum. The op1 and op2 arrays store the two integers to be added, and the sum array will store the result of the addition.

The sum array is one byte longer than the other two arrays to accommodate any carry that may be generated.

The .code section of the code contains the main procedure.

The main procedure first moves the pointers to the two operand arrays and the sum array into the ESI, EDI, and EBX registers, respectively. It then moves the length of the operands into the ECX register.

Next, the main procedure calls the Extended_Add procedure.

The Extended_Add procedure will add the two operands and store the result in the sum array.

After the Extended_Add procedure has finished executing, the main procedure moves the pointer to the sum array into the ESI register and the length of the sum array into the ECX register.

It then calls the Display_Sum procedure to display the sum to the console.

The Display_Sum procedure is a simple procedure that iterates through the sum array and prints each byte to the console.

After the Display_Sum procedure has finished executing, the main procedure calls the Crlf procedure to print a newline character to the console.

The output of the program is the following:

1087 0122C32B0674BB5736

This is the correct sum of the two operands, even though the addition produced a carry. The Extended_Add procedure handles the carry correctly and stores the correct result in the sum array.

The Display_Sum procedure below is related to the Extended_Add procedure you provided in the previous question.

The Display_Sum procedure is used to display the sum of two integers that have been added using the Extended_Add procedure.

It works by iterating through the sum array in reverse order, starting with the high-order byte and working its way down to the low-order byte.

For each byte in the sum array, the Display_Sum procedure calls the WriteHexB procedure to display the byte in hexadecimal format.

Here is a more detailed explanation of the Display_Sum procedure:

```
1092 Display_Sum PROC
                        ; Save registers
1093
         pushad
         ; Point to the last array element
1094
        add esi, ecx
1095
        sub esi, TYPE BYTE
1096
        mov ebx, TYPE BYTE
1097
1098
1099 L1:
        mov al, [esi] ; Get a byte from the array
1100
        call WriteHexB ; Display it in hexadecimal
1101
         sub esi, TYPE BYTE ; Move to the previous byte
1102
        loop L1
1103
1104
                ; Restore registers
1105
         popad
1106
         ret
1107 Display Sum ENDP
```

The pushad instruction saves all of the registers on the stack. The add esi,ecx instruction moves the value of the ECX register into the ESI register.

The sub esi, TYPE BYTE instruction subtracts the size of a byte from the ESI register. This moves the pointer to the last element of the

sum array.

The mov ebx, TYPE BYTE instruction moves the size of a byte into the EBX register. This will be used to loop through the sum array.

The L1: label marks the beginning of the loop.

The mov al,[esi] instruction moves the byte at the current position in the sum array into the AL register. The call WriteHexB instruction calls the WriteHexB procedure to display the byte in hexadecimal format.

The sub esi, TYPE BYTE instruction subtracts the size of a byte from the ESI register. This moves the pointer to the previous byte in the sum array.

The loop L1 instruction loops back to the beginning of the loop if the EBX register is not zero.

The popad instruction restores all of the registers from the stack. The ret instruction returns from the procedure.

The Display_Sum procedure is a good example of how to iterate through an array in reverse order. It is also a good example of how to call another procedure from within a procedure.

Subtract with Borrow

The SBB (subtract with borrow) instruction subtracts both a source operand and the value of the Carry flag from a destination operand.

The possible operands are the same as for the ADC instruction, which means it can be used to subtract operands of any size, including 32-bit, 64-bit, and even 128-bit operands.

The following example code carries out 64-bit subtraction with 32-bit operands:

```
1111 mov edx, 7
1112; upper half
1113 mov eax, 1
1114; lower half
1115 sub eax, 2
1116; subtract 2
1117 sbb edx, 0
1118; subtract upper half
```

This code will subtract the value 2 from the 64-bit integer stored in the EDX: EAX register pair. The subtraction is done in two steps:

The value 2 is subtracted from the lower 32 bits of the integer, which are stored in the EAX register. This subtraction may set the Carry flag if a borrow is required.

The SBB instruction subtracts both 0 and the value of the Carry flag from the upper 32 bits of the integer, which are stored in the EDX register.

Here is a more detailed explanation of the code:

```
1123 mov edx, 7
1124 ; upper half
```

This instruction moves the value 7 into the EDX register. This is the upper 32 bits of the 64-bit integer that we will be subtracting from.

```
1128 mov eax, 1
1129 ; lower half
```

This instruction moves the value 1 into the EAX register. This is the lower 32 bits of the 64-bit integer that we will be subtracting from.

```
01 sub eax, 2
02; subtract 2
```

This instruction subtracts the value 2 from the lower 32 bits of the integer, which are stored in the EAX register. This may set the Carry flag if a borrow is required.


```
10 sbb edx, 0
11 ; subtract upper half
```

This instruction subtracts both 0 and the value of the Carry flag from the upper 32 bits of the integer, which are stored in the EDX register.

After the code has executed, the EDX: EAX register pair will contain the result of the subtraction, which is the value 000000700000001h.

The SBB instruction is a powerful tool for performing multi-byte and multi-word subtraction operations. It can be used to subtract operands of any size, including very large integers.

Figure 7–2 Subtracting from a 64-bit integer using SBB.



Describe the ADC instruction:

The ADC (Add with Carry) instruction is used for addition in assembly language. It adds two operands, along with the value of the Carry flag, and stores the result in the destination operand. If there is a carry from the addition, it sets the Carry flag; otherwise, it clears

it. It is particularly useful for multi-precision arithmetic, where you need to handle carry from previous operations.

Describe the SBB instruction:

The SBB (Subtract with Borrow) instruction is used for subtraction in assembly language. It subtracts the source operand from the destination operand, along with the Borrow flag (Carry flag treated as borrow), and stores the result in the destination operand. If a borrow is generated from the subtraction, it sets the Carry flag; otherwise, it clears it. SBB is often used for multi-precision arithmetic to handle borrows from previous operations.

Values of EDX: EAX after the given instructions execute:

mov edx, 10h loads 16 into EDX.
mov eax, 0A000000h loads A0000000h into EAX. add eax, 20000000h adds
20000000h to EAX without carry. adc edx, 0 adds 0 to EDX along with
any carry. Result: EDX = 0 (no carry), EAX = C0000000h.

Values of EDX: EAX after the given instructions execute:

mov edx, 100h loads 256 into EDX.
mov eax, 8000000h loads 80000000h into EAX.
sub eax, 9000000h subtracts 90000000h from EAX without borrow. sbb
edx, 0 subtracts 0 from EDX along with any borrow.
Result: EDX = FFFFFFFF (due to borrow), EAX = FFFFFFFF.

Contents of DX after the given instructions execute:

mov dx, 5 loads 5 into DX.

stc sets the Carry flag to 1.

mov ax, 10h loads 16 into AX.

adc dx, ax adds AX to DX along with the carry. Result: DX = 1 (due to carry).