

```
#!/bin/bash
```

```
init() {  
    # update packages  
    dnf -y upgrade  
  
    # set hostname  
    hostnamectl hostname Centos-jump-OYL  
  
    # install dnf-automatic  
    dnf -y install dnf-automatic  
  
    # install nano  
    dnf -y install nano  
  
    # install vim  
    dnf -y install vim  
}
```

```
brugere() {  
    # create users  
    echo IyEvYm1uL2Jhc2gKYWRkdXNlciAtcCAnJDYkN216Q1pNNS9\  
ZNUQvU0d6ZyRVM0lMSUQzM09CLzhoMnZBY01MTTFGd1doWTRvRUZ\  
mamRkSFdrWE5LT1QwT0ZQUm5qMjard3MyWGZXcGk1eG84eWZ4eVR\  
YUjdWcTYzMmpyRmZkdHBTMScgcGluZ3UK | base64 -d | bash  
  
    useradd berserk-jump  
    echo "H2-2026-1337" | passwd --stdin berserk-jump  
  
    # create group + add members  
    groupadd allow_ssh  
    usermod -aG wheel,allow_ssh pingu  
    usermod -aG wheel,allow_ssh berserk-jump  
}
```

```
selinux() {  
  
    # set SELinux permissive  
    sed -i 's/SELINUX=enforcing/SELINUX=permissive/' /etc/selinux/config  
}
```

```
allow_ssh() {  
  
    # allow SSH group  
    echo "AllowGroups allow_ssh" >> /etc/ssh/sshd_config  
}
```

```
}

dnf-automatic() {

# Automatic updates config
sed -i 's/upgrade_type = default/upgrade_type = security/'\
/etc/dnf/automatic.conf
sed -i 's/apply_updates = no/apply_updates = yes/' /etc/dnf/automatic.conf

# Enable and start automatic updates
systemctl enable dnf-automatic.timer
systemctl start dnf-automatic.timer

}

firewalld() {

# Internal zone / Add SSH port / Remove services
firewall-cmd --permanent --zone=internal --change-interface=enp2s0
firewall-cmd --permanent --zone=internal --remove-service=cockpit
firewall-cmd --permanent --zone=internal --remove-service=dhcpv6-client
firewall-cmd --permanent --zone=internal --remove-service=mdns
firewall-cmd --permanent --zone=internal --remove-service=samba-client
firewall-cmd --permanent --zone=internal --add-port=22/tcp
firewall-cmd --reload

}

main () {

# main funktion
if ! $(rpm --quiet -q nano); then
init
fi

# bruger funktion
if ! $(id berserk-jump); then
brugere
fi

# SELinux funktion
if ! $(grep -q "SELINUX=permissive" /etc/selinux/config); then
selinux
fi

# Allow_SSH funktion
if ! $(grep -q "AllowGroups allow_ssh" /etc/ssh/sshd_config); then
```

```
allow_ssh
```

```
fi
```

```
# dnf-automatic funktion
```

```
if ! $(rpm --quiet -q dnf-automatic); then
```

```
  dnf-automatic
```

```
fi
```

```
# firewallld funktion
```

```
if ! $(firewall-cmd --list-all --zone=internal | grep enp2s0); then
```

```
  firewallld
```

```
fi
```

```
}
```

```
main
```

```
reboot
```