CSS Fonts

Font Family

The font family of a text is set with the **font-family** property.

Note: If the name of a font family is more than one word, it must be in quotation marks, like: "Times New Roman".

More than one font family is specified in a comma-separated list:

Example

```
p {
    font-family: "Times New Roman";
}
```

Font Style

The font-style property is mostly used to specify italic text.

This property has three values:

- normal The text is shown normally
- italic The text is shown in italics

Example

```
p.normal {
    font-style: normal;
}

p.italic {
    font-style: italic;
}
```

Font Size

The font-size property sets the size of the text.

Always use the proper HTML tags, like <h1> - <h6> for headings and <p> for paragraphs.

The font-size value can be an absolute, or relative size.

```
h1 {
    font-size: 40px;
}
```

```
h2 {
    font-size: 30px;
}

p {
    font-size: 14px;
}
```

Font Weight

The font-weight property specifies the weight of a font:

Example

```
p.normal {
    font-weight: normal;
}

p.thick {
    font-weight: bold;
}
```

Text Color

The color property is used to set the color of the text.

With CSS, a color is most often specified by:

- a color name like "red"
- a HEX value like "#ff0000"
- an RGB value like "rgb(255,0,0)"

Example

```
body {
    color: blue;
}

h1 {
    color: green;
}
```

Text Alignment

The text-align property is used to set the horizontal alignment of a text.

A text can be left or right aligned, centered, or justified.

The following example shows center aligned, and left and right aligned text (left alignment is default if text direction is left-to-right, and right alignment is default if text direction is right-to-left):

Example

```
h1 {
    text-align: center;
}

h2 {
    text-align: left;
}

h3 {
    text-align: right;
}
```

When the text-align property is set to "justify", each line is stretched so that every line has equal width, and the left and right margins are straight (like in magazines and newspapers):

Example

```
div {
    text-align: justify;
}
```

Text Decoration

The text-decoration property is used to set or remove decorations from text.

The value text-decoration: none; is often used to remove underlines from links:

Example

```
a {
    text-decoration: none;
}
```

The other text-decoration values are used to decorate text:

```
h1 {
    text-decoration: overline;
```

```
h2 {
    text-decoration: line-through;
}
h3 {
    text-decoration: underline;
}
```

Text Transformation

The text-transform property is used to specify uppercase and lowercase letters in a text.

It can be used to turn everything into uppercase or lowercase letters, or capitalize the first letter of each word:

Example

```
p.uppercase {
    text-transform: uppercase;
}

p.lowercase {
    text-transform: lowercase;
}

p.capitalize {
    text-transform: capitalize;
}
```

Letter Spacing

The letter-spacing property is used to specify the space between the characters in a text.

The following example demonstrates how to increase or decrease the space between characters:

```
h1 {
    letter-spacing: 3px;
}
```

```
h2 {
    letter-spacing: -3px;
}
```

Line Height

The line-height property is used to specify the space between lines:

Example

```
p.small {
    line-height: 0.8;
}

p.big {
    line-height: 1.8;
}
```

Word Spacing

The word-spacing property is used to specify the space between the words in a text.

The following example demonstrates how to increase or decrease the space between words:

```
h1 {
    word-spacing: 10px;
}

h2 {
    word-spacing: -5px;
}
```