

#### Number bases

```
What is a decimal number system?
```

- 783,412
- $7 \times 10^5 + 8 \times 10^4 + 3 \times 10^3 + 4 \times 10^2 + 1 \times 10^1 + 2 \times 10^0$

How about 3.14159?

•  $3 \times 10^{0} + 1 \times 10^{-1} + 4 \times 10^{-2} + 1 \times 10^{-3} + 5 \times 10^{-4} + 9 \times 10^{-5}$ 

Why do we use decimal? Is there anything fundamental about it?

COPYRIGHT 2024. PAUL HASKELL

Mathematically, nothing fundamentally important about decimal

## Octal number base

#### "Octal" $\rightarrow$ 8

- Digits are 0,1,2,3,4,5,6,7
- Often shown with a leading "0" or a subscript 8
- $0376 = 376_8 = 3 \times 8^2 + 7 \times 8^1 + 6 \times 8^0$  (=  $254_{10}$ )

COPYRIGHT 2024. PAUL HASKELL

## Hexadecimal number base

"Hexadecimal" → 16

- Digits are 0,1,2,3,4,5,6,7,8,9,a,b,c,d,e,f
- Often shown with a leading "0x" or a subscript 16
- $0xfa1 = fa1_{16} = 15 \times 16^2 + 10 \times 16^1 + 1 \times 16^0$

COPYRIGHT 2024. PAUL HASKELL

a=10, b=11, ...f=15

,

## Binary number base

"Binary"  $\rightarrow$  2

- Digits are 0,1
- Often shown with a leading "b" or a subscript 2
- $b1101 = 1101_2 = 1 \times 2^3 + 1 \times 2^2 + 0 \times 2^1 + 1 \times 2^0$

Computer circuits (memory, CPU) work with binary – why?

Octal and hexadecimal are useful to humans

- More compact than binary
- Easily convert 3 or 4 binary digits to/from an octal or hex digit

COPYRIGHT 2024. PAUL HASKELL

# Examples

Decimal	Octal	Hex	Binary
15			
	0300		
		0xfa	
			0111 1010
128			
	077		
		0x100	
			0101 1110

COPYRIGHT 2024. PAUL HASKELL

6

# How are numbers stored in computers?

```
"bit" = "binary digit"
"byte" = 8 "bits"
```

How do we store a char, short, int, long?

- char = 1 byte
- short = 2 bytes
- int = 4 bytes (sometimes 2)
- long = 4 bytes

sizeof() operator

COPYRIGHT 2024. PAUL HASKELL

7

## How are numbers stored in computers?

How do we store -42?

Computers use "2's complement"

- Most significant digit is <u>not</u> 2<sup>7</sup>, 2<sup>15</sup>, 2<sup>31</sup> in a char, short, long
- Most significant digit is -2<sup>7</sup>, -2<sup>15</sup>, -2<sup>31</sup>
- In a char,  $1000\ 0101 = -2^7 + 2^2 + 2^0 = -123_{10}$


If first digit is '1', value is <0

To convert a number to its negative, flip all bits and add +1

COPYRIGHT 2024. PAUL HASKELL

1011 10	10
1111 11	11
1111	L 11

Do -15 two ways: counting up values bit by bit, and as 2's complement of +15 Do 1111 1111 two ways



Answer: either of em, depending on CPU type. "little endian" vs "big endian" Important to know answers if exchanging numbers between computers. Good reasons for each, and the world could not settle on a single answer quickly enough.

## New C syntax

C gives us both regular "signed" and "unsigned" variables

Use keyword unsigned before an integer variable type to make it unsigned

COPYRIGHT 2024. PAUL HASKELL

11

Do sample program. Do casting between them. See sample1.c

How to printf() unsigned values?

"u" for unsigned decimal ("d" for signed decimal, "x" for unsigned hex, "o" for unsigned octal)

"I" for long

"h" for short ("half")

# What is the range?

Data type	Numerical range
char	
unsigned char	$0 \rightarrow 2^8 - 1 = 255$
short	
unsigned short	
int	
unsigned int	
long	
unsigned long	

COPYRIGHT 2024. PAUL HASKELL

12

Do code-along: print lots of char and uchar values. Lots of short and ushort values. Print sizeof()



Available built into Linux and MacOS. On Windows must get from Internet.

Look some up! Is, printf