CheckSum for securecopy.txt

```
[root@be286906ce3e mydir]# cksum securecopy.txt
2766876939 488142 securecopy.txt
```

CheckSum After edit

```
[root@be286906ce3e mydir]# nano securecopy.txt
[root@be286906ce3e mydir]# cksum securecopy.txt
2766876939 488142 securecopy.txt
```

Find command

```
[root@be286906ce3e mydir]# find /root -name AbdullahAlsmail.txt
/root/mydir/mydir2/AbdullahAlsmail.txt
```

Grep for search for word Password

```
[root@be286906ce3e mydir]# man useradd 1> useradd-man.txt
[root@be286906ce3e mydir]# grep -i 'password' useradd-man.txt
        The number of days after a password expires until the account is permanently disabled. A value of 0
        disables the account as soon as the password has expired, and a value of -1 disables the feature.
        Example: -K PASS_MAX_DAYS=-1 can be used when creating system account to turn off password aging, even
        though system account has no password at all. Multiple -K options can be specified, e.g.: -K UID_MIN=100
   -p, --password PASSWORD
        The encrypted password, as returned by crypt(3). The default is to disable the password.
        Note: This option is not recommended because the password (or encrypted password) will be visible by users
        You should make sure the password respects the system's password policy.
        The number of days after a password has expired before the account will be disabled.
        /etc/group (with the same name, same password, and same GID).
        The maximum number of days a password may be used. If the password is older than this, a password change
        The minimum number of days allowed between password changes. Any password changes attempted sooner than
        The number of days warning given before a password expires. A zero means warning is given only upon the
        Shadow password suite configuration.
        can't update password file
[root@be286906ce3e mydir]#
```

Challenge :

```
[root@be286906ce3e ~]# diff /var/log/anaconda/syslog  /root/mydir/securecopy.txt
[root@be286906ce3e ~]# diff /var/log/anaconda/syslog  /root/mydir/securecopy.txt
[root@be286906ce3e ~]# diff /var/log/anaconda/syslog  /root/mydir/securecopy.txt
[root@be286906ce3e ~]#
```

No output for, and I don't know what is the reason.