
Documentation: XLSX Template for Area Importing

I. Main headers

Area_OCode, Area_OName, Area_OName_(translation iso code), Area_ORef, Area_OAltName1, Area_OAltName2, Area_OKind

You can add more levels on areas by changing the level on the headers. Adding levels should be done by descending order. See image below for reference.



Area_3Code	Area_3Name	Area_3Name_en	Area_3Ref	Area_3AltName1	Area_3AltName2	Area_3Kind	Area_2Code	Area_2Name	Area_2Name_en	Area_2Ref
A000001-1-1	Sample Store 01	Sample Store 01	SS1	Sample Store 01	Sample Store 01	Store	A000001-1	Bayombong	Bayombong	BAY
A000001-1-2	Sample Farm 01	Sample Farm 01	SF1	Sample Farm 01	Sample Farm 01	Farm	A000001-1	Bayombong	Bayombong	BAY
A000001-1-3	Sample Store 02	Sample Store 02	SS2	Sample Store 02	Sample Store 02	Store	A000001-1	Bayombong	Bayombong	BAY
A000001-2-1	Sample Farm 02	Sample Farm 02	SF2	Sample Farm 02	Sample Farm 02	Farm	A000001-2	Solano	Solano	SOL
A000001-2-2	Sample Farm 03	Sample Farm 03	SF3	Sample Farm 03	Sample Farm 03	Farm	A000001-2	Solano	Solano	SOL
A000001-2-3	Sample Store 03	Sample Store 03	SS3	Sample Store 03	Sample Store 03	Farm	A000001-2	Solano	Solano	SOL

As you can see here, there is a level 3 area. Thus, makes it a child of level 2 area, then level 2 will be child of level 1 and so on.

II. Translations

You can also add more translations of the area name. Just add the column right after **Area_0Name_en** with same format but change the **'en'** to preferred translation ISO Code.

Reminder:

Make sure the language/s you are adding is/are already activated on Odoo > Settings > Translations > Languages. See image below for reference.



You can also go here to check the right ISO Code.

^{*}Note: Level 0 is important as it was the main parent of all levels.