***** VoiceAttack Virtual Co-Pilot v2.9 *****

The Virtual Co-Pilot is a VoiceAttack profile that will call out **YOUR OWN** checklist items for any aircraft. Simply create a list of checklist items in a text file and point the profile to that file, and the Virtual Co-Pilot will audibly walk you through the checklist items when commanded.

There are two profiles included:

Checklist Template.vap will call out your first checklist item and wait for you to say "Check" before continuing. If you say "Repeat", the last checklist item will be repeated. If a response is not provided within 60 seconds, the virtual co-pilot will ask if you want to exit the checklist (in case you have forgotten to complete or exit a running checklist).

Continuous Checklist Template.vap will call out all checklist items in sequence with a 3 second pause between each, unless you say "*Pause*" or "*Stop*", at which time the call out will stop until you say "*Continue*". The code can easily be modified to change the default pause time between callouts.


Video: https://youtu.be/_9i0EnDm4HA

Follow the three steps below to setup VoiceAttack to use the Virtual Co-Pilot profile. This is a one-time process:


- 1. Create a folder anywhere on your PC named "Checklists".
- 2. Extract the **Virtual Co-Pilot.zip** file to this folder.
- 3. Open VoiceAttack and import either the "Checklist Template.vap" file or the "Continuous Checklist Template.vap" file (or both files if you will want to try/use both options).

Follow the steps below whenever you want to create a set of checklists for an aircraft:


- 1. Open the "/Checklists" folder you created in step 1 above.
- 2. Create a sub-folder and name it the same as your aircraft (e.g. /Checklists/Cessna172)
- 3. Open the **Notepad.exe** program (*or any word processor*), and create a list of checks you want to perform for a particular checklist. Put each check on a separate line.
- 4. Save this file to the aircraft folder you created in step 2, and name the file according to the type of checklist it is for (e.g. *Startup.txt*).
- 5. Repeat steps 3 and 4 for every checklist you want to use for this particular aircraft.
- 6. Once you have created all checklist text files, open the VoiceAttack program and select either the "Checklist Template" file or the "Continuous Checklist Template" profile you imported (step 3 above).



7. Use the **Actions** menu to make a duplicate of the profile.




8. Click the **Edit Profile** icon to edit this new profile, and rename it (*use your aircraft designation e.g. "Cessna172 Checklists"*)




Note: While in *Edit* mode, you will see that your new profile contains only one checklist. You can, rename and duplicate it as needed or desired to create addition checklists.


9. Now that you have a new checklist profile for your aircraft, the easiest way to start is to double-click the default "Open Startup Checklist" item to open it. If you want to use a different voice command for opening the checklist, you will want to modify the "When I say:" text to whatever you want. Otherwise, you can keep the default if it works for you.



10. Next, double-click the second command line (*Set text [~textfile]...*) to open the associated dialog box below. Then click the menu button (...).



11. When the dialog box opens, navigate to the "Checklists/[aircraft]" folder you created, select the checklist text file you want the virtual co-pilot to read from then, click the **Open** button.



12. Click the **OK** button to save command changes then, and click the **Apply** button to save the profile changes. Repeat steps 9-12 for any other checklists you created for this aircraft.

Follow the steps below to use one of your checklists:


- 1. Once you are in your aircraft (with VoiceAttack running in the background with your aircraft profile selected), start the virtual co-pilot by saying the VoiceAttack command assigned to a checklist (e.g. "Open Startup Checklist"). The virtual co-pilot will call out the first check from your list. As previously described, one of the templates will wait for you to say the word "check" or "repeat" before continuing, while the other will pause 3 seconds and then continue automatically.
- 2. When the last checklist item has been called out and you say "check", the virtual co-pilot will say, "Checklist complete".

At any time during the call out you can say "exit checklist" to stop the virtual co-pilot. A tone will be played to confirm that the checklist has been stopped.

<u>Caution</u>: To avoid VoiceAttack sync problems, make sure to either <u>finish</u> a checklist or <u>exit</u> a checklist before invoking a new one. Otherwise, you may hear both at the same time.


Follow the steps below if you want to change the TTS voice:

- 1. With the profile activated in **VoiceAttack**, click the 'Edit Profile' icon to view the code.
- 2. In the code list you will see three separate lines that read, **Say**, '{TXT:~lineOutput}'. Double-click one of these lines to open the TTS dialog box. There you can use the "Voice" drop-down box provided to change voices. Do this for all three instances.



Follow the steps below if you want to change the timeout timer in the standard template:

- 1. With the profile activated in **VoiceAttack**, click the 'Edit Profile' icon to view the code.
- 2. In the code list you will see the highlighted line below. Double-click this line and change the timeout value.



Follow the steps below if you want to change the pause time in the "Continuous" template:

- 1. With the profile activated in **VoiceAttack**, click the 'Edit Profile' icon to view the code.
- 2. In the code list you will see two lines that reads, "Pause 3 seconds". Simply double-click these lines and change the value to whatever you want to use.

