Tomcat en Windows y NetBeans

Descargar .zip (primera opción) de la sección de descargas de https://tomcat.apache.org/

Download

Which version?

Tomcat 10

Tomcat 9

Tomcat 8

Tomcat Migration Tool

for Jakarta EE

Tomcat Connectors

Tomcat Native

Taglibs

Archives

8.5.75

Please see the README file for packaging information. It explains what


Binary Distributions

- Core:
 - o <u>zip (pgp, sha512)</u>
 - o tar.gz (pgp, sha512)
 - o 32-bit Windows zip (pgp, sha512)
 - 64-bit Windows zip (pgp, sha512)
 - 32-bit/64-bit Windows Service Installer (pgp, sha512)
- Full documentation:
 - tar.gz (pgp, sha512)
- Deployer:

Vamos a Services > Servers, le damos al boton secundario y a "Add Server..."



Elegimos la ruta de la carpeta con los archivos de Tomcat:




Para obtener el usuario y la contraseña hay que ir, dentro de la carpeta especificada, a conf/tomcat_users.xml y especificar el usuario de la siguiente forma:

```
<user username="tomcat" password="tomcat" roles="tomcat"/>
```

Iniciar el servidor:



Tras introducir el usuario y contraseña especificados anteriormente, se inicia Tomcat:



Tomcat en Ubuntu

Actualizar paquetes:

```
admindwes@OLP-USED:~$ sudo apt update
```

Instalar kit de desarrollo de Java:

```
admindwes@OLP-USED:~$ sudo apt install default-jdk
```

Descargar e instalar Tomcat:

```
admindwes@OLP-USED:~$ sudo apt install tomcat9 tomcat9-admin
```

Comprobar que el puerto 8080 está habilitado:

```
admindwes@OLP-USED:~$ ss -punta
Netid State Recv-Q Send-Q Local Address:Port Peer Address:Port Process
udp UNCONN 0
                                    0
                                                  127.0.0.53%10:53
                                                                                                     0.0.0.0:*
tcp LISTEN 0
                                     4096 127.0.0.53%10:53
                                                                                                     0.0.0.0:*
tcp LISTEN 0 128
tcp ESTAB 0 0
tcp TIME-WAIT 0 0
tcp LISTEN 0 70
tcp LISTEN 0 151
                                                                                                     0.0.0.0:*
                                                               0.0.0.0:22
                                                  192.168.0.120:22
                                                                                            192.168.0.20:1146
                                                   192.168.0.120:55904 91.189.88.142:80
                                                                          *:33060
                                                                                                                *:*
                                                                          *:3306
         LISTEN 0
                                      100
                                                                                                                *:*
                                                                          *:8080
tcp
        LISTEN 0
                                                                          *:80
                                                                                                                *:*
                                     511
tcp
        LISTEN 0
                                      128
                                                                     [::]:22
                                                                                                           [::]:*
tcp
admindwes@OLP-USED:~$ ss -puta
Netid State
                        Recv-Q Send-Q Local Address:Port
                                                                                          Peer Address:Port Process

        Net1d
        State
        RecV-Q
        Send-Q
        Local
        Address: Fort

        udp
        UNCONN
        0
        127.0.0.53%lo:domain

        tcp
        LISTEN
        0
        4096
        127.0.0.53%lo:domain

        tcp
        LISTEN
        0
        128
        0.0.0.0:ssh

        tcp
        ESTAB
        0
        64
        192.168.0.120:ssh

        tcp
        TIME-WAIT
        0
        192.168.0.120:55904
        9

        tcp
        LISTEN
        0
        70
        *:33060

        tcp
        LISTEN
        0
        151
        *:mysql

        tcp
        LISTEN
        0
        511
        *:http-alt

                                                                                             0.0.0.0:*
                                                                                                     0.0.0.0:*
                                                             192.168.0.120:55904 91.189.88.142:http
                                                                                                                * * *
                                                                                                                *:*
                                                                                                                *:*
                                                                                                                *:*
tcp LISTEN 0
                                    511
                                                                        *:http
         LISTEN
                         0
                                       128
                                                                                                          [::]:*
tcp
                                                                   [::]:ssh
admindwes@OLP-HSFD.~S
```

← → C ♠ No es seguro | 192.168.0.120:8080

It works!

If you're seeing this page via a web browser, it means you've setup Tomcat successfully. Congratulations!

This is the default Tomcat home page. It can be found on the local filesystem at: /var/lib/tomcat9/webapps/R00T/index.html

Tomcat veterans might be pleased to learn that this system instance of Tomcat is installed with CATALINA_HOME in /usr/share/tomcat common/RUNNING.txt.gz.

Los archivos de tomcat se encuentran en /etc/tomcat9