

R1#

R1#

R1#

R1#

R1#

R1#config terminal

Enter configuration commands, one per line. End with CNTL/Z.

R1(config)#interface ethernet e0/0

^

% Invalid input detected at '^' marker.

R1(config)#interface e0/0

R1(config-if)# ip add 50.0.1.129 255.255.255.192

R1(config-if)#no shutdown

R1(config-if)#exit

R1(config)#interface e0/1

R1(config-if)#ip add 50.0.1.193 255

*Sep 10 08:37:36.663: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped

R1(config-if)#ip add 50.0.1.193 255.255.255.252

R1(config-if)#no shutdown

R1(config-if)#exit

R1(config)#

Enter configuration commands, one per line. End with CNTL/Z.

R2(config)#

R2(config)#

R2(config)#interface e0/0

R2(config-if)#ip add 50.0.0.1

*Sep 10 08:44:28.701: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Con

R2(config-if)#ip add 50.0.1.1 255.255.255.128

R2(config-if)#no shutdown ^

% Invalid input detected at '^' marker.

R2(config-if)#no shutdown

R2(config-if)#exit

R2(config)#interface e0/1

R2(config-if)#ip add 50.0.1.194 ip add 255.255.255.252 ^

% Invalid input detected at '^' marker.

R2(config-if)#ip add 50.0.1.194 255.255.255.252

R2(config-if)#no shutdown

R2(config-if)#exit

R2(config)#interface e0/2

R2(config-if)#ip add 50.0.1.197 255.255.255.252

R2(config-if)#no shutdown

R2(config-if)#exit

R2(config)#

```
R3(config)#interface e0/0
R3(config-if)#ip add 50.0.0.1 255.255.255.0
R3(config-if)#no shutdown
R3(config-if)#exit
R3(config)#int e0/1
R3(config-if)#ip add 50.0.1.198 255.255.255.252
R3(config-if)#no shutdown
R3(config-if)#exit
R3(config)#
```

```
R1(config)#
R1(config)#
R1(config)#
R1(config)#
R1(config)#ip route 50.0.1.0 255.255.255.128 50.0.1.194
R1(config)#ip route 50.0.1.196 255.255.255.252 50.0.1.194
R1(config)#ip route 50.0.0.0 255.255.255.0 50.0.1.194
R1(config)#no shutdown
      ^
```

% Invalid input detected at '^' marker.

```
R1(config)#exit
```

```
R1#sh
```

*Sep 10 09:04:41.760: %SYS-5-CONFIG_I: Configured from console by console

```
R1#show ip route
```

Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
E1 - OSPF external type 1, E2 - OSPF external type 2
i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
ia - IS-IS inter area, * - candidate default, U - per-user static route
o - ODR, P - periodic downloaded static route, H - NHRP, l - LISP
a - application route
+ - replicated route, % - next hop override, p - overrides from Pfr

Gateway of last resort is not set

50.0.0.0/8 is variably subnetted, 7 subnets, 5 masks

```
S      50.0.0.0/24 [1/0] via 50.0.1.194
S      50.0.1.0/25 [1/0] via 50.0.1.194
C      50.0.1.128/26 is directly connected, Ethernet0/0
L      50.0.1.129/32 is directly connected, Ethernet0/0
C      50.0.1.192/30 is directly connected, Ethernet0/1
L      50.0.1.193/32 is directly connected, Ethernet0/1
S      50.0.1.196/30 [1/0] via 50.0.1.194
```

```
R1#
```

```
R2(config)#
R2(config)#
R2(config)#
R2(config)#
R2(config)#
R2(config)#
R2(config)#
R2(config)#ip route 50.0.1.128 255.255.255.192 50.0.1.193
R2(config)#ip route 50.0.0.0 255.255.255.0 50.0.1.198
R2(config)#exit
R2#
```

*Sep 10 09:07:33.539: %SYS-5-CONFIG_I: Configured from console by console

R2#show ip route

Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
 D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
 N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
 E1 - OSPF external type 1, E2 - OSPF external type 2
 i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
 ia - IS-IS inter area, * - candidate default, U - per-user static route
 o - ODR, P - periodic downloaded static route, H - NHRP, l - LISP
 a - application route
 + - replicated route, % - next hop override, p - overrides from PfR

Gateway of last resort is not set

```
50.0.0.0/8 is variably subnetted, 8 subnets, 5 masks
S      50.0.0.0/24 [1/0] via 50.0.1.198
C      50.0.1.0/25 is directly connected, Ethernet0/0
L      50.0.1.1/32 is directly connected, Ethernet0/0
S      50.0.1.128/26 [1/0] via 50.0.1.193
C      50.0.1.192/30 is directly connected, Ethernet0/1
L      50.0.1.194/32 is directly connected, Ethernet0/1
C      50.0.1.196/30 is directly connected, Ethernet0/2
L      50.0.1.197/32 is directly connected, Ethernet0/2
```

R2#

```
R3(config)#
R3(config)#
R3(config)#
R3(config)#
R3(config)#
R3(config)#
R3(config)#
R3(config)#
R3(config)#
R3(config)#
R3(config)#ip route 0.0.0.0 0.0.0.0 50.0.1.197
R3(config)#exit
R3#s
```

*Sep 10 09:15:56.610: %SYS-5-CONFIG_I: Configured from console by console

```
R3#show ip route
```

Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
E1 - OSPF external type 1, E2 - OSPF external type 2
i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
ia - IS-IS inter area, * - candidate default, U - per-user static route
o - ODR, P - periodic downloaded static route, H - NHRP, l - LISP
a - application route
+ - replicated route, % - next hop override, p - overrides from PfR

Gateway of last resort is 50.0.1.197 to network 0.0.0.0

```
S* 0.0.0.0/0 [1/0] via 50.0.1.197
C 50.0.0.0/8 is variably subnetted, 4 subnets, 3 masks
C 50.0.0.0/24 is directly connected, Ethernet0/0
L 50.0.0.1/32 is directly connected, Ethernet0/0
C 50.0.1.196/30 is directly connected, Ethernet0/1
C 50.0.1.198/32 is directly connected, Ethernet0/1
```

R1#

R1#ping 50.0.1.0

Type escape sequence to abort.

Sending 5, 100-byte ICMP Echos to 50.0.1.0, timeout is 2 seconds:

!!!!!!

Success rate is 100 percent (5/5), round-trip min/avg/max = 1/1/1 ms

R1#ping 50.0.0.0

Type escape sequence to abort.

Sending 5, 100-byte ICMP Echos to 50.0.0.0, timeout is 2 seconds:

!!!!!!

Success rate is 100 percent (5/5), round-trip min/avg/max = 1/1/1 ms

R1#

```
R2#  
R2#ping 50.0.1.128  
Type escape sequence to abort.  
Sending 5, 100-byte ICMP Echos to 50.0.1.128, timeout is 2 seconds:  
!!!!!  
Success rate is 100 percent (5/5), round-trip min/avg/max = 1/1/1 ms  
R2#ping 50.0.0.0  
Type escape sequence to abort.  
Sending 5, 100-byte ICMP Echos to 50.0.0.0, timeout is 2 seconds:  
!!!!!  
Success rate is 100 percent (5/5), round-trip min/avg/max = 1/1/1 ms  
R2#
```

R3#

R3#ping 50.0.1.128

Type escape sequence to abort.

Sending 5, 100-byte ICMP Echos to 50.0.1.128, timeout is 2 seconds:

!!!!!!

Success rate is 100 percent (5/5), round-trip min/avg/max = 1/1/1 ms

R3#ping 50.0.1.0

Type escape sequence to abort.

Sending 5, 100-byte ICMP Echos to 50.0.1.0, timeout is 2 seconds:

!!!!!!

Success rate is 100 percent (5/5), round-trip min/avg/max = 1/1/1 ms

R3#

R1(Config)#

R1(config)#

R1(config)#ip dhcp pool prdep

R1(dhcp-config)#network 50.0.1.0 255.255.255.128

R1(dhcp-config)#default-router 50.0.1.1

R1(dhcp-config)#exit

R1(config)#

R2#

R2#

R2#

R2#config t

Enter configuration commands, one per line. End with CNTL/Z.

R2(config)#interface e0/0

R2(config-if)#ip helper-address 50.0.1.193

R2(config-if)#

VPC-2>

VPC-2> ip dhcp

DDORA IP 50.0.1.2/25 GW 50.0.1.1

VPC-2> █

I

```
R1(config)#  
R1(config)#  
R1(config)#ip dhcp pool sales dep  
R1(dhcp-config)#network 50.0.0.0 255.255.255.0  
R1(dhcp-config)#default-router 50.0.0.1  
R1(dhcp-config)#exit  
R1(config)#
```

R3#

R3#

R3#config t

Enter configuration commands, one per line. End with CNTL/Z.

R3(config)#int e0/0

R3(config-if)#ip helper-address 50.0.0.193

R3(config-if)#ip helper-address 50.0.1.193

R3(config-if)#

VPC-3>

VPC-3> ip dhcp

DD

Can't find dhcp server

VPC-3> ip dhcp

DDORA IP 50.0.0.2/24 GW 50.0.0.1

VPC-3> █