

Card scheme	RID	Product	PIX	AID
<u>Visa</u>	A000000003	Visa credit or debit	1010	A0000000031010
		<u>Visa Electron</u>	2010	A0000000032010
		<u>V PAY</u>	2020	A0000000032020
		Plus	8010	A0000000038010
<u>MasterCard</u>	A000000004	MasterCard credit or debit	1010	A0000000041010
		<u>MasterCard</u> ²	9999	A0000000049999
		<u>Maestro (debit card)</u>	3060	A0000000043060
		<u>Cirrus</u> (interbank network)ATM card only	6000	A0000000046000
<u>MasterCard</u>	A000000005	<u>Maestro UK</u> (formerly branded as <u>Switch</u>)	0001	A0000000050001
<u>American Express</u>	A000000025	American Express	01	A00000002501
<u>LINK (UK) ATM network</u>	A000000029	ATM card	1010	A0000000291010
<u>CB (France)</u>	A000000042	CB (Credit or Debit card)	1010	A0000000421010
		CB (Debit card only)	2010	A0000000422010
<u>JCB</u>	A000000065	Japan Credit Bureau	1010	A0000000651010
<u>Dankort (De nmark)</u>	A000000121	Debit card	1010	A0000001211010
<u>CoGeBan (Italy)</u>	A000000141	PagoBANCOMAT	0001	A0000001410001
<u>Diners Club/ Discover</u>	A00000 0152	Diners Club/Discover	3010	A0000001523010
<u>Banrisul (Brazil)</u>	A00000 0154	Banricompras Debito	4442	A0000001544442
<u>SPAN2 (Saudi Arabia)</u>	A00000 0228	SPAN	1010	A00000022820101010
<u>Interac (Canada)</u>	A00000 0277	D ebit card	1010	A0000002771010
<u>Discover</u>	A000000324	ZIP	1010	A0000003241010
<u>UnionPay</u>	A000000333	Debit	010101	A000000333010101
		Credit	010102	A000000333010102
		Quasi Credit	010103	A000000333010103
		Electronic Cash	010106	A000000333010106
<u>ZKA (Germany)</u>	A000000359	<u>Girocard</u>	1010028001	A0000003591010028001
<u>EAPS BANCOMAT (Italy)</u>	A000000359	PagoBANCOMAT	10100380	A00000035910100380
<u>Verve (Nigeria)</u>	A000000371	Verve	0001	A0000003710001
<u>The Exchange Network</u> ATM Network	A000000439	ATM card	1010	A0000004391010
<u>RuPay (India)</u>	A000000524	RuPay	1010	A0000005241010