Functional Requirements for List Boxer version 1.98

Date: Version 15.10.12

O.1

Functional Requirements for List Boxer version

| Revision Sheet | | | |
|----------------|---|------------|--|
| Name Surname | Date | Data | |
| | A draft version of the document was created | 15.10.2012 | |

Contents

| Revision Sheet | |
|--|---|
| Purpose of the Document | |
| Functional Requirements | 5 |
| 1. System Requirements | 5 |
| 2. Functional Requirements for List Boxer version 1.98 | 5 |
| 2.1. Main Features | 5 |
| 2.2. Operating Modes | 6 |
| 2.3. Controls | 6 |
| 2.4. Display Management (Filters) | 7 |
| 2.5. List Sorting | 7 |
| 2.6. Adding a String to the List | 7 |
| 2.7. Deleting Information | 8 |
| 2.8. Undo Last Action | 8 |
| 2.9. Contextual Help | 8 |
| 2.10. Calling the Program Description | |
| 2.11. Shortcuts | 8 |

Functional Requirements for List Boxer version 1.98 Date: Version 1.5.10.12 0.1

Purpose of the Document

This document is intended for the **testing team**.

Functional Requirements

1. System Requirements

1.1. **Operating system:** Windows XP SP2

1.2. Minimum system requirements:


- Processor: Intel Celeron 440 @ 1.00 GHz

- RAM: 1 GB

Video card: 64 MB

- Minimum free disk space: 100 KB

2. Functional Requirements for List Boxer version 1.98



2.1. Main Features

- Create universal alphanumeric lists
- Edit lists
- Save lists as files on disk
- Open lists
- Delete lists

Functional Requirements for List Boxer version 1.98

Date: Version 15.10.12 0.1

2.2. Operating Modes

• alfabetic:

- Alphabetic:

- Data type: Letters (uppercase, lowercase, Latin)
- String length: 1–8
- Activation: Checkbox "Alphabetic"
- Other characters are not allowed in this mode

- Numeric:

Data type: DigitsRange: 0 to 9999

- Activation: Checkbox "Numeric"

- Mixed:

- Data type: Letters (uppercase, lowercase, Latin) and digits (0 to 9999)
- Activation: Both "Numeric" and "Alphabetic" checkboxes

2.3. Controls

- Buttons:

- "Clear List" clears all entered information
- "Add to List" transfers input field data into the list
- **Option buttons** (grouped under "Sort Order"):
 - "Ascending"
 - "Descending"
- **Checkboxes** (grouped under "Symbols"):
 - "Alphabetic"
 - "Numeric"

2.4. Display Management (Filters)

- Filters available only if one of the three modes is active
- Filter types depending on mode:
 - o Alphabetic:
 - "<none>", "All", "a-m", "n-z"
 - Numeric:
 - "<none>", "All", "0–100", "101–200", "201–300", "301–9999"
 - Mixed:
 - All available filters

• Filter details:

- o "<none>": blocks display of all items
- o "All": displays all list items depending on selected mode
- o "a-m": shows items starting with letters in this range
- o "n-z": shows items starting with letters in this range

2.5. List Sorting

- **Ascending**: via "Ascending" option button
- **Descending**: via "Descending" option button
- Numbers are treated as character strings when sorted

Functional Requirements for List Boxer version 1.98

Date: Version 15.10.12 0.1

- 2.6. Adding a String to the List
 - Press the "Add to List" button
 - Press ENTER

2.7. Deleting Information

- At any moment, all entered data can be deleted
- 2.8. Undo Last Action
 - Use the **Undo** command from the "Edit" menu
- 2.9. Contextual Help
 - Available for every command

2.10. Calling the Program Description

- Via the "Help" menu

2.11. Shortcuts

- Open: Ctrl+O
- Save as: Ctrl+S
- Exit: Ctrl+Q
- Copy: Ctrl+C
- Cut: Ctrl+X
- Paste: Ctrl+V
- **Undo:** Ctrl+Z
- Close: Alt+F4
- **Contextual Help:** F1