SDN Mini Project

Port Status Monitoring Tool

Pavan E Naik

PES2UG24CS343

4 ‘F’



```
pavan_e_naik@LAPTOP-KK8H   pavan_e_naik@LAPTOP-KK8H:

Windows PowerShell
Copyright (C) Microsoft Corporation. All rights reserved.

Install the latest PowerShell for new features and improvements! https://aka.ms/PSWindows

PS C:\Users\pavan e naik> wsl
pavan_e_naik@LAPTOP-KK8H55E2:/mnt/c/Users/pavan e naik$ cd ~
pavan_e_naik@LAPTOP-KK8H55E2:~$ cd pox
pavan_e_naik@LAPTOP-KK8H55E2:~/pox$ nano port_monitor.py
pavan_e_naik@LAPTOP-KK8H55E2:~/pox$ ./pox.py log.level --DEBUG port_monitor
POX 0.7.0 (gar) / Copyright 2011-2020 James McCauley, et al.
DEBUG:core:POX 0.7.0 (gar) going up...
DEBUG:core:Running on CPython (3.12.3/Mar 3 2026 12:15:18)
DEBUG:core:Platform is Linux-6.6.87.2-microsoft-standard-WSL2-x86_64-with-glibc2.39
WARNING:version:POX requires one of the following versions of Python: 3.6 3.7 3.8 3.9
WARNING:version:You're running Python 3.12.
WARNING:version:If you run into problems, try using a supported version.
INFO:core:POX 0.7.0 (gar) is up.
DEBUG:openflow.of_01:Listening on 0.0.0.0:6633
INFO:openflow.of_01:[00-00-00-00-00-01 1] connected
INFO:port_monitor:Switch 1 connected
INFO:port_monitor:Port 1 added
INFO:port_monitor:Port 1 is UP
INFO:port_monitor:Port 2 added
INFO:port_monitor:Port 2 is UP
DEBUG:openflow.of_01:1 connection aborted
INFO:port_monitor:Port 1 is DOWN
INFO:port_monitor:Port 2 is DOWN
INFO:port_monitor:Port 1 is DOWN
INFO:port_monitor:Port 1 is UP
INFO:port_monitor:Port 2 is DOWN
INFO:port_monitor:Port 2 is UP
```

```
pavan_e_naik@LAPTOP-KK8H5   pavan_e_naik@LAPTOP-KK8H
Windows PowerShell
Copyright (C) Microsoft Corporation. All rights reserved.

Install the latest PowerShell for new features and improvements! https://aka.ms/PSWindows

PS C:\Users\pavan e naik> wsl
pavan_e_naik@LAPTOP-KK8H55E2:/mnt/c/Users/pavan e naik$ sudo mn --topo single,2 --controller remote --switch ovsk
[sudo] password for pavan_e_naik:
*** Creating network
*** Adding controller
Unable to contact the remote controller at 127.0.0.1:6653
Connecting to remote controller at 127.0.0.1:6633
*** Adding hosts:
h1 h2
*** Adding switches:
s1
*** Adding links:
(h1, s1) (h2, s1)
*** Configuring hosts
h1 h2
*** Starting controller
c0
*** Starting 1 switches
s1 ...
*** Starting CLI:
mininet> link s1 h1 down
mininet> link s1 h2 down
mininet> link s1 h1 up
mininet> link s1 h2 up
mininet>
```

https://github.com/PavanENaik/CN-Project.git