







Router>enable

Router#show ip interface brief

Interface	IP-Address	OK?	Method	Status	Protocol
Ethernet0/0	unassigned	YES	TFTP	administratively down	down
Ethernet0/1	unassigned	YES	TFTP	administratively down	down
Ethernet0/2	unassigned	YES	TFTP	down	down
Ethernet0/3	unassigned	YES	TFTP	down	down

Router#configure terminal

Enter configuration commands, one per line. End with CNTL/Z.

Router(config)#interface ethernet 0/0

Router(config-if)#ip address 50.0.0.1 255.0.0.0

Router(config-if)#no shutdown

Router(config-if)#exit

*Aug 21 10:13:29.374: %LINK-3-UPDOWN: Interface Ethernet0/0, changed state to up

*Aug 21 10:13:30.375: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/0, changed state to up

```
Router(config)#interface ethernet 0/1
Router(config-if)#ip address 60.0.0.1 255.0.0.0
Router(config-if)#no shutdown
Router(config-if)#
*Aug 21 10:16:04.122: %LINK-3-UPDOWN: Interface Ethernet0/1, changed state to up
*Aug 21 10:16:05.126: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/1, changed state to up
Router(config-if)#exit
Router(config)#exit
Router#
*Aug 21 10:16:20.511: %SYS-5-CONFIG I: Configured from console by console
```

```
Router#show ip interface brief
```

Interface	IP-Address	OK?	Method	Status	Protocol
Ethernet0/0	50.0.0.1	YES	manual	up	up
Ethernet0/1	60.0.0.1	YES	manual	up	up
Ethernet0/2	unassigned	YES	TFTP	down	down
Ethernet0/3	unassigned	YES	TFTP	down	down

Router#show ip route

Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP

D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area

N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2

E1 - OSPF external type 1, E2 - OSPF external type 2

i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2

ia - IS-IS inter area, * - candidate default, U - per-user static route

o - ODR, P - periodic downloaded static route, H - NHRP, l - LISP

a - application route

+ - replicated route, % - next hop override, p - overrides from PfR

Gateway of last resort is not set

50.0.0.0/8 is variably subnetted, 2 subnets, 2 masks

C 50.0.0.0/8 is directly connected, Ethernet0/0

L 50.0.0.1/32 is directly connected, Ethernet0/0

60.0.0.0/8 is variably subnetted, 2 subnets, 2 masks

C 60.0.0.0/8 is directly connected, Ethernet0/1

L 60.0.0.1/32 is directly connected. Ethernet0/1

```
QEMU (Win1)
```

```
C:\Documents and Settings\user>route add 60.0.0.0 mask 255.0.0.0 50.0.0.1
```

```
C:\Documents and Settings\user>route print
```

```
=====
```

```
Interface List
```

```
0x1 ..... MS TCP Loopback interface
```

```
0x2 ...50 fe 9c 09 4f 00 ..... Intel(R) PRO/1000 MT Network Connection - Packet Scheduler Miniport
```

```
=====
```

```
Active Routes:
```

Network	Destination	Netmask	Gateway	Interface	Metric
50.0.0.0		255.0.0.0	50.0.0.10	50.0.0.10	10
50.0.0.10		255.255.255.255	127.0.0.1	127.0.0.1	10
50.255.255.255		255.255.255.255	50.0.0.10	50.0.0.10	10
60.0.0.0		255.0.0.0	50.0.0.1	50.0.0.10	1
127.0.0.0		255.0.0.0	127.0.0.1	127.0.0.1	1
224.0.0.0		240.0.0.0	50.0.0.10	50.0.0.10	10
255.255.255.255		255.255.255.255	50.0.0.10	50.0.0.10	1

```
=====
```

```
Persistent Routes:
```

```
None
```

