







SCENARIO :1 ALLOW 10.0.0.0 TO COMMUNICATE ONLY INSTAGRAM SERVER USING PORT NO 80




```
R1#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
R1(config)#$ 100 permit tcp 10.0.0.0 0.0.0.255 180.0.0.10 0.0.0.0 eq 80
R1(config)#int e0/0
R1(config-if)#ip access-group 100 in
R1(config-if)#exit
R1(config)#
```






SCENARIO 2: ALLOW PING COMMUNICATION FROM 10.0.0.10 TO INSTAGRAM SERVER

A terminal window titled 'R1' with standard window controls (minimize, maximize, close). The terminal shows the following commands and prompts:

```
R1(config)#access-list 100 permit icmp 10.0.0.10 0.0.0.0 180.0.0.10 0.0.0.0
R1(config)#exit
R1#
```



```
QEMU (Win-1)
C:\WINDOWS\system32\cmd.exe
Microsoft Windows XP [Version 5.1.2600]
(C) Copyright 1985-2001 Microsoft Corp.

C:\Documents and Settings\user>ping 180.0.0.10


Pinging 180.0.0.10 with 32 bytes of data:

Reply from 180.0.0.10: bytes=32 time=7ms TTL=60
Reply from 180.0.0.10: bytes=32 time=4ms TTL=60
Reply from 180.0.0.10: bytes=32 time=4ms TTL=60
Reply from 180.0.0.10: bytes=32 time=3ms TTL=60


Ping statistics for 180.0.0.10:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 3ms, Maximum = 7ms, Average = 4ms

C:\Documents and Settings\user>_
```


SCENARIO 3: ALLOW 10.0.0.20 TO COMMUNICATE ONLY FACEBOOK SERVER USING SSH AND HTTP





```
R1#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
R1(config)# 100 permit tcp 10.0.0.20 0.0.0.0 180.0.0.20 0.0.0.0 eq 22
```



```
R1(config)# 100 permit tcp 10.0.0.20 0.0.0.0 180.0.0.20 0.0.0.0 eq 80
R1(config)#exit
R1#
```









SCENARIO 4 : ALLOW 10.0.0.0 TO COMMUNICATE SNSITE SERVER USING HTTP


```
R1#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
R1(config)# 100 permit tcp 10.0.0.0 0.0.0.255 192.52.234.100 0.0.0.0 eq 80
R1(config)#
```




SCENARIO 5:ALLOW 11.0.0.0 TO COMMUNICATE INSTAGRAM AND FACEBOOK SERVER USING HTTP


A terminal window titled 'R2' with standard window controls (minimize, maximize, close) in the top right corner. The terminal displays a series of configuration commands for a network device. The prompt is 'R2#conf t', followed by a message 'Enter configuration commands, one per line. End with CNTL/Z.' The commands entered are: 'R2(config)# 100 permit tcp 11.0.0.0 0.0.0.255 180.0.0.10 0.0.0.0 eq 80', 'R2(config)# 100 permit tcp 11.0.0.0 0.0.0.255 180.0.0.20 0.0.0.0 eq 80', 'R2(config)#int e0/0', 'R2(config-if)#ip access-group 100 in', and 'R2(config-if)#exit'.

```
R2#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R2(config)# 100 permit tcp 11.0.0.0 0.0.0.255 180.0.0.10 0.0.0.0 eq 80
R2(config)# 100 permit tcp 11.0.0.0 0.0.0.255 180.0.0.20 0.0.0.0 eq 80
R2(config)#int e0/0
R2(config-if)#ip access-group 100 in
R2(config-if)#exit
```






SCENARIO 6: ALLOW 11.0.0.10 TO PING FACEBOOK SERVER



SCENARIO 7: ALLOW 11.0.0.10 TO PING SNLAB SERVER

```
R2#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R2(config)#$ 100 permit icmp 11.0.0.10 0.0.0.0 192.52.234.200 0.0.0.0
R2(config)#exit
```



SCENARIO 8: ALLOW 11.0.0.0 TO ACCESS SNLAB SERVER

```
R2#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R2(config)#$ 100 permit ip 11.0.0.0 0.0.0.255 192.52.234.200 0.0.0.0
R2(config)#exit
R2#
*Oct  2 12:03:51.263: %SYS-5-CONFIG_I: Configured from console by console
```

