The Ghastly Grab

Screen Layout & Interaction

Main Menu ..... pg. 2

Help Screen (how to play) ..... pg. 3

Sound Setting Screen ..... pg. 3

Credits Screen ..... pg. 3

Main Game Play Screen ..... pg. 4

Inventory Screen ..... pg. 5

Losing Screen ..... pg. 5

Winning Screen ..... pg. 6

Game Play

Movement ..... pg. 7

Boundary Checking ..... pg. 7

Collision Detection ..... pg. 8

Scare Meter ..... pg. 8

Final Scare ..... pg. 9

Inventory ..... pg. 9

Covering Items ..... pg. 9

Usable Items ..... pg. 9

Unusable Items ..... pg. 10

Rooms – 7 ..... Pg. 10

Game Assets

Art Assets (42) ..... pg. 13

Sound Assets (29) ..... pg. 15

Screens



Main menu (MEG 50% / KM 50%)



Clickable options:

- Play Button - If this button mouse clicked, go to game start
- Help button - If this button mouse clicked, go to help screen
- Sound settings Button - If this button mouse clicked, go to sound screen
- Credits & Sources button - If this button mouse clicked, go to credits and sources screen

Non clickable:

- Title of game
- Background

Help screen (how to play) (MEG 50% / KM 50%)

Clickable options:

- Back Button - If this button mouse clicked, go to main menu screen

Non clickable:

- Instruction Text on how to play:
    - “Use arrow keys or WASD to move the player”
    - “Collect items on your robbery list when they appear on screen”
    - “Collect other items that could be useful, as seen in inventory”
    - “If you're stuck, try inspecting the inventory for a few helpful tips”
    - “Oh, and try not to get too scared :)”

Sound setting screen (MEG 50% / KM 50%)

Clickable options:

- Music (On/Off) - if off clicked when on active music is turned off and off slider becomes colored, on slider becomes un-colored. If on clicked when off active music is turned on and on slider becomes colored, off slider becomes un-colored
- Sound Effects (On/Off) - if off clicked when on active music is turned off and off slider becomes colored, on slider becomes un-colored. If on clicked when off active music is turned on and on slider becomes colored, off slider becomes un-colored
- Back Button - goes to main menu

Credits screen (MEG 50% / KM 50%)

Clickable options:

- Back button - If this button mouse clicked, go to main menu screen

Non clickable:

- Names of Makers
- Origin of any non-original assets

Main Game Play screen (MEG 50% / KM 50%)



The main gameplay screen will display the player's current location and orientation. The current location of all visible items and current room / background

The bottom of the screen contains a nav bar containing: a list of items to be acquired (with updated current status of acquisition, struck-through when acquired), the scare meter at its current status visible below and inventory button

Clickable options:

- Inventory button - If this button mouse clicked, go to inventory screen
- Different Items - acquires usable and non-usable items and moves covering items out of the way

Non clickable:

- Items list
- Background
- Scare meter

Inventory screen (MEG 50% / KM 50%)



Clickable options:

- Usable Items - If this button mouse clicked and item not yet possessed, play audio read out of tip
- Back Button - If this button clicked, go to main menu screen

Mouse Hoverable options:

- Usable Items - If this button mouse hovered, tip will appear on tip radio

Non clickable:

- The tips text (that changes based on mouse hover location)
    - Key - “Turn over every…”
    - Crowbar - “Put away amongst fauna”
    - Safe Combination Note - “Not a recipe!”
    - Shovel - “Whatever would you use this for?”
- Text Describing the usable item
- Background

Losing / Jumpscare screen (MEG 50% / KM 50%)

Non clickable:

- Jump-scare animation
- ‘You Lose’ text after animation over

Win screen / credits (MEG 50% / KM 50%)

Non clickable:

- Background
- ‘You Win’ text
- credits

Game Play

Movement (MEG 50% / KM 50%)

- Keep moving as long as key pressed (arrow keys or WASD)
    - Up arrow or W will move the player up on the screen
    - Down arrow or S will move the player down on the screen
    - Left arrow or A will move the player left on the screen
    - Right arrow or A will move the player right on the screen
- Player can only move in one direction at a time
- Player will move at a constant speed
- Glow on floor indicates door to next room, this is where the player can move off screen to the next room

Bound Checking for Movement (MEG 50% / KM 50%)



The yellow box represents the 800x450 window that the user sees in the main gameplay screen. The green stick figure represents a few of the possible locations of the character and the red stick figure represents locations that the character cannot be in. The HUD element will be drawn AFTER the character so that only the character's head will appear when the character moves to the bottom part of the screen (The HUD will cover other parts)



A <T> Rect will be located at the 'leg' of the character (bottom 20% of the character sprite). Additionally, the 'floor' will have 4 <T> Rects attached to it as highlighted in the photo and listed below:

- The rectangular floor that is visible to the user (in yellow)
- The 2 slanted rectangles on either sides (in red)
- The rectangle below the visible floor (in green)

The movement status of the player will be updated on respective button click discussed in 'Movement' of Game Play System. When any of the four 'floor' Rects no longer contains the 'leg' Rect, the last movement will be reversed (basically teleporting player back in bounds). This is a general case. In cases where there is a door/exit at the bottom of the visible screen, collision detection is needed

Collision Detection for Movement (MEG 50% / KM 50%)

In rooms where there is an exit, the player entering the bounds of a <T> Rect (the exit) will change the room (the background and other on-screen elements). This is done by checking if the exit <T> Rect contains the 'leg' Rect of the player sprite discussed above. If the check returns true, the room is changed

Scare Meter (MEG 50% / KM 50%)

- With every wrongful click comes a one in three chance of a 'scare'
- The scare meter will go up by one cell (the scare meter is 10 cells long) when a scare happens as well as a spooky sound effect plays
- When the scare meter half full - opportunity for the Final jump-scare and LOSS

    - On five cells filled - one in five chances
    - On Six cells filled - one in four chances
    - On seven cells filled - one in three chances
    - On eight cells filled - one in two chances
    - On nine cells filled - full chance

Final scare (MEG 50% / KM 50%)

- When a final scare is triggered, a jumpscare will appear on screen, animate then freeze on the final screen, during this a loud sound effect will play

Inventory (MEG 50% / KM 50%)

- Opened by clicking inventory button (bag icon) on main game screen
- On opening inventory, crackle SFX plays on loop
- Tips radio static animation on top plays
- If item not had, when mouse hovered over item, tip on acquiring item pops up
- When game starts, all usable items are greyed out
- When user finds usable item, they become colored

Covering items (MEG 50% / KM 50%)

- If covering item clicked it disappears from screen and a non-covering item is revealed
- Include:
    - Doormat (outside; in front of door)
    - Box (greenhouse; right corner)
    - Safe (bedroom; left hand side of bed)
    - Kitchen cabinet Door (kitchen; on cabinet)

Usable items (MEG 50% / KM 50%)

- If usable item clicked it disappears from screen and is highlighted in the inventory panel (except shovel which triggers the final jump-scare instead)
- If an item clicked that needs a usable item when the player does not have it nothing will happen - using booleans
- Include:
    - Key (outside; below doormat):
        - Use: opens house front door
    - Crowbar (greenhouse; inside box):
        - Use: grab the saber off the wall
    - Safe combination numbers note (kitchen; inside cabinet):

        - Use: open safe
    - Shovel (greenhouse: used as a table leg)
        - Use: distraction – if attempted to be used it will play the final scare and end the game

Unusable items (MEG 50% / KM 50%)

- When clicked it disappears from screen and is crossed off from list at bottom of screen
- When all are collected game is won - win screen plays
- Include:
    - Watch (bedroom; nightstand)
    - Bracelet (bedroom; on vanity)
    - Purse (bedroom; on bed)
    - Medicine (bathroom; on sink)
    - Antique weaponry - saber (hallway; on wall left half of room)
    - Power tool (greenhouse; on ground)
    - Vase (sitting room; on mantel)
    - Playing cards (sitting room; coffee table)
    - Expensive coat (hallway; hanging on coat hanger)

Rooms – 7 (MEG 50% / KM 50%)

Outside (starting area)



Greenhouse



Hallway



Living Room



Kitchen



Bedroom



Bathroom



Assets

Art Assets (42)
(MEG 50% / KM 50%)

Character Assets - Movement animation (6)

Mirroring images when possible, to cut down on asset creation that only need to be created once

- Right and left, two assets need to be made one still standing and one with a raised leg
- Backwards, two assets need to be made one still standing and one with a raised leg
- Forwards, two assets need to be made one still standing and one with a raised leg

Items (17)

- Usable items (4)
    - Key
    - Crowbar
    - Safe combination numbers note
    - Shovel
- Unusable items (9)
    - Watch
    - Bracelet
    - Purse
    - Drugs
    - Antique weaponry
    - Power tool
    - Vase
    - Playing cards
    - Expensive coat
- Covering items (4)
    - Doormat
    - Box
    - Safe
    - Kitchen cabinet Door

Background (10)

- Outside will be playable from one point of views, one asset needed
- Hallway will be playable from two point of views, two asset needed
- Kitchen will be playable from one point of views, one asset needed
- Living room will be playable from one point of views, one asset needed
- Bathroom will be playable from one point of views, one asset needed
- Bedroom will be playable from two point of views, two asset needed
- Green house will be playable from one point of views, one asset needed

Jumpscare / End (4)

- Two animation screens (possibly just one tilting)
- End of animation hold screen
- One death screen

Win screen (1)

- Winning screen that transfers into credits

Tips Radio - Static (4)

- One screen for when tip is being shown
- Three animation screens

Audio Assets (8 MUSIC, 17 SFX and 4 VOICELINES)
(MEG 50% / KM 50%)

- BG Music for Menu - 1 MUSIC
- Menu buttons click sound - 1 SFX

- Spooky audio (For wrong click) - 8 SFX
- Final jump-scare visceral scream - 1 SFX
- All other item achieved - 1 SFX
- Covering item clicked - 1 SFX
- Item used audio for each usable item - 4 SFX
- Door opening sound - 1 SFX

- BG Music for gameplay (except inventory screen) - 1 MUSIC
- Room specific score for all rooms - 4 MUSIC:
    - Fireplace sound for sitting room
    - Crickets sound for Greenhouse
    - Faucet drip sound for Kitchen and bathroom
    - Jazz Record Player for bedroom (~https://www.youtube.com/watch?v=ovLzn_EIBd8)

- Inventory Screen Audio - 1 MUSIC and 4 VOICELINES:
    - Crackling sound - 1 MUSIC
    - Voiceover for each tip - 4 VOICELINES

- BG Music for Win Screen - 1 MUSIC