



Module 04

User Profiles and Home Directory



1. Roaming Profiles

- 1.1. User Profile Management
- 1.2. Create Roaming Profile
- 1.3. View Roaming Profile on Client

2. Home Directory

- 2.1. What is Home Dir
- 2.2. Admin Accesses User HomeDir
- 2.3. Map Drive HomeDir to User
- 2.4. Copy Roaming Profile

3. Mandatory Profile

- 3.1. Create Mandatory Profile
- 3.2. Verify Mandatory Profile on Client



1. Roaming Profiles

1.1. User Profile Management




User Profiles is a collection of files and data, it stores the settings that users use or make changes on the desktop, such as setting the desktop settings, start menu, program item and personal data.



In Windows Server 2025, User Profiles are categorized as follows:

- Local Profile
- Roaming Profile
- Mandatory Profile

1.1. User Profile Management (Cont.)



Local Profile:

Created and stored on a stand-alone computer (Local Computer).



Roaming Profile:

Created by the Administrator and stored in a shared folder on the server and downloaded to the client machine every time user's logon. Users can change or save this Roaming Profile, and it will be updated on the server after users log off.



1.1. User Profile Management (Cont.)

- Mandatory Profile:
 - is a Read-only Roaming Profiles created by the Administrator and stored in a shared folder on the server and downloaded to the client every time users log on. Users can change any settings during logon, but after log off it will not update on the server, it only remembers what the Administrator has set.





1.2. Create Roaming Profile

- Step 1: Create a **Folder** name **HomeDir** > Right click and select **Properties** > Click **Share** button





1.2. Create Roaming Profile (Cont.)

- Step 2: Select **Everyone** > Click **Add** button > Select **Everyone** > Choose **Read/Write** > Click **Share** button





1.2. Create Roaming Profile (Cont.)

- Step 3: Click **Done** > Click **Close**



1.2. Create Roaming Profile (Cont.)

- Step 4: Click **Tools** menu > Click **Active Directory Users and Computers** > Create a New User > Right click on **created user** > Select **Properties**



1.2. Create Roaming Profile (Cont.)

- Step 5: Click **Profile** tab > In **Profile path**: Enter **\\WIN-SERVER\HomeDir\%username%** > Click **Apply** > Click **OK**

Reach Makara Properties

Member Of	Dial-in	Environment	Sessions
Remote control	Remote Desktop Services Profile	COM+	
General	Address	Account	Profile
Telephones	Organization		

User profile

Profile path:

Logon script:

Home folder

☒ Local path:

☐ Connect: To:

OK Cancel **Apply** Help

Reach Makara Properties

Member Of	Dial-in	Environment	Sessions
Remote control	Remote Desktop Services Profile	COM+	
General	Address	Account	Profile
Telephones	Organization		

User profile

Profile path:

Logon script:

Home folder

☒ Local path:

☐ Connect: To:

OK Cancel Apply Help

1.2. Create Roaming Profile (Cont.)



\\WIN-SERVER\HomeDir\%username%



\\WIN-SERVER => \\Server Name





\HomeDir => \Share Name



\%username% => \Current Username



1.3. View Roaming Profile on Client

- Step 1: On client PC, **login** with configured user account > Go to **This PC** and right click > Choose **Properties**




1.3. View Roaming Profile on Client (Cont.)

- Step 2: Click **System** > **about** > **Advanced System Settings** > Enter **administrator** name and **password** > Click **Yes** button



1.3. View Roaming Profile on Client (Cont.)

- Step 3: Under Profiles section, click **Settings** button
> Find configured user, you will see its type is **Roaming** > Click **OK** to close





2. Home Directory



2.1. What is HomeDir?

Each user must have their own Home Directory and Profiles. Home Directory is a personal folder for each user to store various data on the server.

After we have created the user's profile to the account, the next step is to create another Home Directory so that those accounts have a drive to store data on the server.




2.2. Admin Accesses User HomeDir

- Step 1: **Login** with configured user on Windows Client
> Search this path (**\\WIN-SERVER\HomeDir**) >
Click it to open






2.2. Admin Accesses User HomeDir (Cont.)

- Step 2: Right click on **user folder** > Select **Properties** > Click **Edit** button > Click **Add** button




2.2. Admin Accesses User HomeDir (Cont.)

- Step 3: type **administrator** in text area > Click **Check Names** button > Select **Administrator** > Click **OK** > Click **OK**




2.2. Admin Accesses User HomeDir (Cont.)

- Step 4: Check **Allow Full control** > Click **OK** > Click **OK**





2.2. Admin Accesses User HomeDir (Cont.)

- Step 5: Go to C:\HomeDir\13052.V6 on Windows Server you will see user profile folders display in user **HomeDir**






2.3. Map Drive HomeDir to User

- Step 1: Click **Tools** menu > Click **Active Directory Users and Computer** > Right click on a **user** > Select **Properties**




2.3. Map Drive HomeDir to User (Cont.)

- Step 2: Select **Profile** tab > Choose **Connect: (X, Y, or Z)** depend on your Drive letter you want > In To text field, type **\\WIN-SERVER\HomeDir\13052.V6** > Click **Apply** > Click **OK** > Click **Yes** button > Click **OK**





2.3. Map Drive HomeDir to User (Cont.)

- Step 3: **Login** on **Windows Client** with configured user > Go to **This PC**, you will see a share drive map to this user account




2.4. Copy Roaming Profile

- Step 1: Go to **Windows Server** Right click on a user > Select Copy > Change User information > Click Next button



2.4. Copy Roaming Profile (Cont.)

- Step 2: Set **Password** and **Confirm password** > Check **Password never expires** > Click **Next** button > Click **OK**



Copy Object - User

Create in: makara.com/Users

Password:

Confirm password:


☐ User must change password at next logon

☐ User cannot change password

☒ Password never expires

☐ Account is disabled

< Back Next > Cancel



Copy Object - User

Create in: makara.com/Users

When you click Finish, the following object will be created:


Copy from: Reach Makara

Full name: Ly Chandara

User logon name: 18888@makara.com

The password never expires.

< Back Finish Cancel





Active Directory Domain Services

! The \\WIN-SERVER\HOMEDir\13052.V6 home folder was not created because it already exists. The user account has been created with this home folder value but you might want to select a different name, or make sure that the user has full access privileges to the existing one.

OK


2.4. Copy Roaming Profile (Cont.)

- Step 3: Right click on **created user** > Change **Profile path**, **Home folder** Connect: and To: change ID > Click **OK**



2.4. Copy Roaming Profile (Cont.)

- Step 4: Go to **Windows Client** Login with configured user that Copy profile and open **This PC** to see the result






3. Mandatory Profile




3.1. Create Mandatory Profile

- Step 1: On **Windows Server** Create a **Folder (MAN)**
 - > Right click choose **Properties** > Click **Share** button






3.1. Create Mandatory Profile (Cont.)

- Step 2: Click **Find people** > Type **Authent** > Click **Check Names** button > Select **Authenticated Users** > Click **OK**





3.1. Create Mandatory Profile (Cont.)

- Step 3: Click **OK** > Click **Share** button > Click **Done**



3.1. Create Mandatory Profile (Cont.)

- Step 4: Click **Tools** menu > **Active Directory Users and Computers** > Create a **User** to configure Mandatory Profile > Right click on this **User** > Select **Properties**



Opens the properties dialog box for the current selection.

3.1. Create Mandatory Profile (Cont.)

- Step 5: Click **Profile** tab > type in **Profile path:** \\WIN-SERVER\MAN\%username% > Click **Apply** > **OK**

Ly Panha Properties

Member Of	Dial-in	Environment	Sessions
Remote control	Remote Desktop Services Profile	COM+	

General Address Account **Profile** Telephones Organization

User profile

Profile path: \\WIN-SERVER\MAN\%username%

Logon script:

Home folder

☒ Local path:

☐ Connect: To:

OK Cancel **Apply** Help

Ly Panha Properties

Member Of	Dial-in	Environment	Sessions
Remote control	Remote Desktop Services Profile	COM+	

General Address Account **Profile** Telephones Organization

User profile

Profile path: \\WIN-SERVER\MAN\19999

Logon script:

Home folder



☒ Local path:

☐ Connect: To:

OK **OK** Cancel Apply Help


3.1. Create Mandatory Profile (Cont.)

- Step 6: On **Windows Client** Login with **MAN user** > Open **Run** and type **\\WIN-SERVER\MAN** > Click **OK**






3.1. Create Mandatory Profile (Cont.)

- Step 7: Right click on man user folder > Click Properties > On **Security** Tab > Click Edit





3.1. Create Mandatory Profile (Cont.)

- Step 8: Click **Add** button > type **Admini** > Click **Check Names** button > Select **Administrator** > Click **OK**




3.1. Create Mandatory Profile (Cont.)

- Step 9: Click **OK** > Check **Allow Full control** > Click **OK** > Create any file in **Desktop** to generate user profile folder




3.1. Create Mandatory Profile (Cont.)

- Step 10: On **Windows Client** Sign out and Login again with the previous user > Open **Run** and type **\\WIN-SERVER\MAN** > Click **OK**




3.1. Create Mandatory Profile (Cont.)

- Step 11: Go to MAN user profile > Click View tab > Check Hidden items > You will see a NTUSER.DAT




3.1. Create Mandatory Profile (Cont.)

- Step 12: Shutdown or Sign Out the Client PC, and Login to Server and go to C:\MAN > Click View > Check File name extensions and Hidden items





3.1. Create Mandatory Profile (Cont.)

- Step 13: Change NTUSER.DAT to NTUSER.MAN





3.1. Create Mandatory Profile (Cont.)

- Step 14: Click **Yes** button > Open **Run** and type **gpupdate /force** > Click **OK**




3.2. Verify Mandatory Profile on Client

- Step 1: Go to **Client Login** with **MAN user** > Go to **Run** type **sysdm.cpl** > click **OK** (hit Enter)





3.2. Verify Mandatory Profile on Client (Cont.)

- Step 2: Enter administrator name and password > Click Yes button





3.2. Verify Mandatory Profile on Client (Cont.)

- Step 3: Click **Tab Advance** and Under **User Profiles** click **Settings** button > You will see this user type is **Mandatory** > Click **Cancel** button





3.2. Verify Mandatory Profile on Client (Cont.)


- Step 4: On Desktop please create or copy some files to **make data changes** > Sign out



3.2. Verify Mandatory Profile on Client (Cont.)

- Step 5: **Login** with **MAN** user again > You will see this **Desktop** still **keep files, folders, or icons** have the **same numbers** or location as previous session





Thank You.