


Multi-factor authentication — My Cash Pilot

AHN Media · internal bookkeeping system · screenshots taken 16 September 2026

Multi-factor authentication is required for every account, with no exemption, and is enforced by the database as well as the application. The factor in use is a time-based one-time password from an authenticator app.

1. Sign-in — the first factor

Every account is created by an administrator for a named member of staff; there is no public sign-up. A correct password alone does not grant access to any financial data.



The screenshot shows a web interface for 'Two-factor sign-in' on the 'My Cash Pilot' system. The page has a light gray background. In the center, there is a white card with rounded corners. At the top of the card, the title 'Two-factor sign-in' is displayed in bold, with 'My Cash Pilot' underneath it in a smaller font. Below the title, a prompt reads 'Enter the six-digit code from your authenticator app.' This is followed by a text input field containing the digits '1 2 3 4 5 6'. A blue 'Verify' button is positioned below the input field. At the bottom of the card, there is a link for users who have lost their authenticator, stating 'Lost your authenticator? [Contact support](#) — an administrator can reset it after confirming who you are.' and a 'Sign out' link.

Two-factor sign-in

My Cash Pilot

Enter the six-digit code from your authenticator app.

1 2 3 4 5 6


Verify

Lost your authenticator? [Contact support](#) — an administrator can reset it after confirming who you are.

[Sign out](#)

2. The second factor is required at every sign-in

After the password, the user must enter the six-digit code from their authenticator app (TOTP, RFC 6238). Until this step succeeds the session remains at assurance level AAL1, and a PostgreSQL row-level security policy refuses every row to an AAL1 session — so the requirement holds even for a request made directly to the database, not only in the interface. Plaid Link can only be reached from a page behind this screen.



The image shows a two-factor sign-in screen for 'My Cash Pilot'. The screen has a light gray background. At the top, the title 'Two-factor sign-in' is centered, followed by the subtitle 'My Cash Pilot'. Below this is a white card with rounded corners. Inside the card, the text 'Enter the six-digit code from your authenticator app.' is displayed. Below this text is a text input field with a light gray border and a light gray background, containing the placeholder text '1 2 3 4 5 6'. Below the input field is a blue button with the text 'Verify' in white. Below the button, the text 'Lost your authenticator? [Contact support](#) — an administrator can reset it after confirming who you are.' is displayed. At the bottom of the card, the text '[Sign out](#)' is displayed.

3. Enrolment — required before any data is shown

A new account cannot reach any page until it has enrolled an authenticator. The QR code shown here was generated for a temporary account created solely for this screenshot, which was deleted immediately afterwards. A lost authenticator is reset by an administrator only after confirming the person's identity.

Set up two-factor sign-in

My Cash Pilot

My Cash Pilot holds the company's bank data and can send payroll, so every account signs in with a password **and** a code from an authenticator app. This takes about a minute and is only done once.

1. Open an authenticator app — Google Authenticator, Microsoft Authenticator, 1Password, Authy or similar.

2. Scan this code with it.



▶ Cannot scan? Enter this key instead

3. Enter the six-digit code the app shows.

1 2 3 4 5 6

Turn on two-factor sign-in

[Sign out](#)