For gate entities in active and inactive statuses, you can only edit the **Contact Person**, **Phone Number**, and **Arrival Lead Time** fields. All the other fields are non-editable similar to the edit option in gate in the **Manage Entities** app.

- **Business Working Hours**

  This worksheet contains all the information in the gate **Business Hours** tab in the **Manage Entities** app. You can view the following columns:

  - Gate reference
  - Time period reference
  - Start date
  - End date
  - Working days
  - Start time
  - End time

  Note that you can edit all the fields in this worksheet similar to the edit option in gate in the **Manage Entities** app.

Upload Gates Microsoft Excel

To upload the gates in a Microsoft Excel file, perform the following:

1. You can use the gates file that you previously downloaded using the **Download** option to edit the existing data.

   Alternatively, you can download the template by choosing **Gate** > **Excel** > **Export Template** option to add new gates. This template contains the same worksheets and columns similar to the downloaded gates Microsoft Excel file. However, it does not contain any data.

   Note that you can only use either the template or the downloaded file to upload into the system.

2. Upload the Excel file by choosing **Gate** > **Excel** > **Upload**.

   Upload entities dialog box appears.

3. Select the edited file that you want to upload from your computer and choose **Proceed**.

   The system displays the confirmation message indicating the number of gate entities that will be uploaded. It will also display the error log if some of the entities are in error state. You can download the error log to investigate the issue.

4. Choose **Confirm** to upload the entities.

   Displays whether the entities are uploaded. If they are uploaded, you can view them in the **Gate** tab in the app.

ℹ Note

There are a few columns that are hidden in the worksheets. These columns contain technical information. You cannot edit these columns

Adding of **Enable Sharing** option is currently not available in the Microsoft Excel file.

You cannot edit the status of the gate in the Microsoft Excel file. You can only change the status in the **Manage Entities** app.

You can only upload Microsoft Excel files with a maximum of 2500 entries.

Defining Yard Settings

Yard settings define operational parameters such as business hours, gates, and docking locations, crucial for efficient yard management.

To define the settings for a yard, proceed as follows:

1. Choose the **Yard** tab on the left pane.
2. Choose the **Add Yard** button.

   The create yard pane appears on the right.

   a. Define settings for the following sections:

   b. **Details**

   c. **Business Hours**

   d. **Gates**

   e. **Docking Locations**
3. Choose **Save** to save the yard settings as a draft. Choose **Save and Activate** to activate the yard settings.

ℹ Note

The following fields cannot be changed any longer after the yard was activated:

- Yard ID
- Location ID
- Description
- Address
- Time Zone

Details

Enter the following information in the details section:

- **Location ID**

  Select a location ID. You maintain location master data in the **Manage Locations** app.
- **Time Zone**

  Enter a time zone.
- **Yard ID**

  Specify a yard ID.
- **Remarks**

  You can enter the additional information about the yard in this section.

Business Hours

Choose the add icon in this section to add an entry of business hours.

> **Note**
> You can add only one entry of business hours for a yard.

Enter the following information:

- **Period**

  Specify the duration for which the entry of business hours is valid.

- **Working Days**

  Specify the working days of the yard.

- **Working Hours**

  Specify the working hours for the specified working days.

  To add another entry of validity period, choose the add icon. You can create up to 10 entries per validity period.

Gates

Choose the add icon in this section to add entries of gates. The system displays the list of active gates in the same time zone that you have maintained in the **Manage Entities** app. You can select the gates that you want to add to the yard.

> **Note**
> The system displays active gates in the same time zone that are either shared with yards or active gates in the same time zone that are yet to be associated with a yard.

Once you add one or more gates to the yard, you must use the **Assign Default** button to assign one of the inbound gates and one of the outbound gates as the default gate. Note that if you assign an inbound/outbound gate as the default gate, you need not assign any other gates as the default gate. If you do not assign the default gates, then the system does not allow you to activate the yard.

Docking Locations

Choose the add icon in this section to add entries of docking locations. The system displays the list of active docking locations in the same time zone that you have maintained in the **Manage Entities** app. You can select the docking locations that you want to add to the yard.

> **Note**
> The system displays only the active docking locations in the same time zone.

Viewing a Yard

Displays detailed information about a yard's status, location, business hours, gates, and docking locations.

To view the yard settings, proceed as follows:

1. Choose the **Yard** tab on the left pane.
2. Enter the yard ID in the search bar on the left pane to search for a specific yard.
3. Choose a yard from the results.

The system displays the detail view of the settings on a right pane.

The detail view consists of a header and other sections.

Header

The header section displays the following information:

- **Yard ID**
- **Location ID**
- **Yard Icon**

  Displays the yard icon.

  Also displays a shared sign on this icon when a yard has enabled sharing with business partners. You can view the sharing details by choosing this icon. The system displays the **Yard ID**, **Location ID**, **Shared By**, and **Permissions**.

- **Status**

  Displays one of the following statuses:

  - **Draft**

    This status appears after you create a yard and choose the **Save** button. You can delete a yard only when it is in a draft status.

  - **Active**

    This status appears when you activate a draft or an inactive yard or when you choose the **Save and Activate** button while creating a new yard.

  - **Inactive**

    This status appears when you deactivate a yard by choosing the **Deactivate** button. Note that deactivation may take some time and you may have to refresh your page to get the updated status. You cannot deactivate a yard that is associated with active gates.

  - **Decommissioned**

    This status appears when you close a yard by choosing the **Decommission** button. You can only decommission yards that are in the inactive status. Once you decommission a yard, you cannot activate it or perform any actions.

Details

The details section displays the following information:

- **Location ID**
- **Description**

  Displays the location description. The system retrieves this information once from the master data of the associated location when the location has been assigned to the yard.

- **Address**

  Displays the location address. The system retrieves this information once from the master data of the associated location when the location has been assigned to the yard.

- **Time Zone**

Displays the time zone of the location. The system retrieves this information once from the master data of the associated location when the location has been assigned to the yard.

- **Yard ID**
- **Remarks**

  Displays additional information about the yard in this section.

Share Entity

You can share the yard details with your business partner. Based on the settings you provide here, the business partner can either view or view and edit the yard details.

This section displays the following information:

- **Created By**

  Displays the details of who created the yard sharing.

- **Share Entity With**

  Displays the business partners with whom the yard has been shared with.

- **Permissions**

  Displays whether the business partner can only view or edit the yard settings.

ℹ Note

You can only share active yards with your business partners. That is, when you create a yard, save, and activate the setting, you can edit the yard settings and add sharing details.

As a prerequisite, you must establish a relationship with the business partner (shipper) with whom you want to share your yard. To do so, use the **Invite Business Partners** app and add a new invitee as a shipper. The shipper must operate in the same data center as you. For more information, see Add New Business Partners.

Business Hours

This section displays the business hours of the yard. This section displays the following information:

- **Period**

  Displays the duration for which the entry of business hours is valid.

- **Working Days**

  Displays the working days of the yard.

- **Working Hours**

  Displays the working hours for the specified working days.

Gates

Displays the list of gates in the same time zone that are associated with the yard. This section displays the following information for each entry:

- **Gate ID**

- **Description**
- **Direction**
- **Working Hours**
- **Default Gate**

  Displays whether the gate is a default gate

Docking Locations

Displays the list of docking locations that are associated with the yard. This section displays the following information for each entry:

- **Docking Location ID**
- **Description**
- **Working Hours**

Uploading and Downloading Yards

SAP Business Network Freight Collaboration enables you to simplify the entity management process especially when you have lot of entities to be processed.

You can view, edit, and upload entities using a Microsoft Excel file. This feature enables you to work on multiple entries simultaneously thereby saving a lot of time. You can download and upload the entities in Microsoft Excel format.

In the **Yard** tab, in the worklist area on the left, you can view the **Excel** button. When you choose this button, you can select one of the following options:

- **Download**

  You can download all the yard entities in Microsoft Excel.

- **Upload**

  You can upload the edited Microsoft Excel template containing the yards that you want to add.

- **Export Template**

  You can download this Microsoft Excel template file to add the yards and upload it in the system.

Download Yards Microsoft Excel

The downloaded yards Microsoft Excel file contains the following worksheets:

- **Yard**

  This worksheet contains all the information in the yard **Details** tab in the **Manage Entities** app. You can view the following columns:

  - Yard reference

    As the yard information has been split across different worksheets in this Microsoft Excel file, the system has created this reference ID in the Microsoft Excel file. When you switch to another worksheet, you can use this reference ID to logically map the relevant data.

  - Yard ID

- Location ID
- Time zone

> **Note**
>
> For yard entities in draft status, you can edit all the above fields.
>
> For yard entities in active and inactive statuses, all the above fields are non-editable similar to the edit option in yard in the **Manage Entities** app.

- **Business Working Hours**

  This worksheet contains all the information in the yard **Business Hours** tab in the **Manage Entities** app. You can view the following columns:

  - Yard reference
  - Time period reference
  - Start date
  - End date
  - Working days
  - Start time
  - End time

  Note that you can edit all the fields in this worksheet similar to the edit option in yard in the **Manage Entities** app.

- **Docking Location Association**

  This worksheet contains the associations between the yard and docking locations. You can view the **Yard Reference** and the associated **Docking Location Reference** in this worksheet.

  Note that you can edit both the above fields are editable.

- **Docking Location**

  This worksheet contains the **Docking Location Reference**, **Docking Location ID**, and **Description**.

  Note that all the fields in this worksheet are non-editable similar to the edit option in yard in the **Manage Entities** app.

- **Gate Association**

  This worksheet contains the associations between the yard and gate. You can view the **Yard Reference** and the associated **Gate Reference** in this worksheet.

  Note that you can edit both the above fields are editable.

- **Gate**

  This worksheet contains the **Gate Reference**, **Gate ID**, **Description**, and **Direction**.

  Note that all the fields in this worksheet are non-editable similar to the edit option in yard in the **Manage Entities** app.

Upload Yards Microsoft Excel

To upload the yards in a Microsoft Excel file, perform the following:

1. You can use the yards file that you previously downloaded using the **Download** option to edit the existing data.

Alternatively, you can download the template by choosing Yard > Excel > Export Template option to add new yards. This template contains the same worksheets and columns similar to the downloaded yards Microsoft Excel file. However, it does not contain any data.

Note that you can only use either the template or the downloaded file to upload into the system.

2. Upload the Excel file by choosing Yard > Excel > Upload.

   Upload entities dialog box appears.

3. Select the edited file that you want to upload from your computer and choose Proceed.

   The system displays the confirmation message indicating the number of yard entities that will be uploaded. It will also display the error log if some of the entities are in error state. You can download the error log to investigate the issue.

4. Choose Confirm to upload the entities.

   Displays whether the entities are uploaded. If they are uploaded, you can view them in the Yard tab in the app.

ℹ Note

There are a few columns that are hidden in the worksheets. These columns contain technical information. You cannot edit these columns.

Adding of Enable Sharing option is currently not available in the Microsoft Excel file.

You cannot edit the status of the yard in the Microsoft Excel file. You can only change the status in the Manage Entities app.

You can only upload Microsoft Excel files with a maximum of 2500 entries.

Manage Dock Appointments

You, as a shipper, can use this app to manage (view, edit, cancel) the dock appointments that carriers have booked for loading or unloading services in the docking locations of your organization.

In this app, you can also apply instance-based authorization. This helps you to restrict the shippers who can access the dock appointments of a certain docking location to only those that are involved in the management of that location.

The main features of this app include:

- Reschedule a dock appointment
- Cancel a dock appointment
- Create a dock appointment
- Reserve a time slot

ℹ Note

To use this app, you must add one or several roles to your role collection. The required role templates and application identifiers are described in the Available Roles for Shippers section of the Administration Guide for Shippers.

Docking Locations

You can view all docking locations in the overview page. The system displays the details of each docking location in a card format. You can filter the docking locations based on the Location ID, Description, and Address.

Each docking location card displays the following information:

- **Location ID**

  Displays the location ID of the docking location. Note that the system retrieves the docking location details that you have created in the **Docking Location Settings** app.

- **Description**

  Displays the description for the docking location that you have specified in the **Docking Location Settings** app.

- **Address**

  Displays the address of the docking location that you have specified in the **Docking Location Settings** app.

- **Booked Appointments**

  Displays the number of future active appointments booked in this docking location in the current week.

- **Ready for Booking**

  Displays the number of documents that are ready for booking an appointment in the current week.

- **Current Week Slot Utilization**

  Displays the number of appointments in this docking location for the current week.

Detail View (Manage Dock Appointments)

The detail view of a docking location consists of a calendar view and a table view.

Calendar View

When you choose a docking location in the worklist page, the system by default opens the calendar of appointments for the docking location.

You can view the appointment calendar for the entire docking location in the **All** tab. You can also view the individual appointment calendar for each loading point available in the selected docking location by choosing the various tabs with the loading point ID. Non-working hours are displayed as greyed-out in 15-minute intervals, based on the validity period of the loading point. You can switch between the day, week, and month view for the loading point calendars. Based on the view that you choose, the system displays the appointments for the specific day, week, or month. Note that the system applies this setting across all the loading point calendars in the docking location. The system displays all the appointments for the day along with the freight order details. Note that in the month view of the calendar, if there is no space to display all the appointments, the system displays some of the appointments in a dialog box. You can also resize this dialog box as desired.

In the calendar view, you can view an icon in the upper right corner of the calendar. When you choose this icon, the system displays the details of calendar and appointments color coding.

The following are the descriptions of various icons used in the calendar view.

Icon	Description
	Arrival

Icon	Description
	Check-In Begin
	Check-In On Hold
	Checked In
	Loading
	Unloading
	Executed
	Overdue
	Grouped
	Blocked Time

You can drag and drop an appointment in the calendar to reschedule an appointment.

ℹ Note

You can drag and drop to reschedule only those appointments which have time slots in multiples of 30 minutes (for example, 9:00 – 10:00 or 9:30 – 10:30). If the time slots are not in multiples of 30 minutes (for example, 8:45 – 9:45 or 8:15 – 9:15), then you cannot drag and drop to reschedule appointment. However, you can select the appointment and change the time using input boxes.

You can use the static search option on the header area to search for booked appointments based on a given freight order ID, appointment ID, or reference document ID. The search is globally conducted for all loading points in the **All** tab, and separately conducted in the individual appointment calendar for each loading point. The number of matches found in the search is indicated in parentheses, like **(1)**, at the end of the tab name, and the best appointment match is displayed in the **Maintain Appointment** view. If you have, for example, several appointments that are based on the same freight order, you get several hits for the same freight order, and the system randomly selects one appointment to be displayed as the best match.