2. On the **Create New Location** page, enter the following details:

    - **Source**: Source of the location. Valid values are:

        - **SAP SCM Logistic Location**: Locations from one of the following systems:

            - SAP Extended Warehouse Management

            - SAP Transportation Management

        - **SAP ERP Location**: Locations from an SAP ERP system

        - **Others**: Locations from other systems

    - **Location Type**: Type of the location

      This field is available when **Source** is set to **SAP SCM Logistic Location**.

    - **Object Type**: Business purpose of a location.

      This field is configurable when **Source** is set to **SAP ERP Location** or **Others**. When **Source** is set to **SAP SCM Logistic Location**, the system automatically sets **Object Type** to **Logistic Location**.

      Valid values for the Object Type field are::

        - **Business Partner**

        - **Customer**

        - **Plant**

        - **Shipping Point**

        - **Supplier**

      If none of the values above fits the location's business purpose, you can change **Source** to **SAP SCM Logistic Location** as an alternative. This will set **Object Type** to **Logistic Location** at the backend and make **Location Type** configurable. The **Location Type** field provides you with a broader list of types pertaining to various business purposes, such as port and hub.

      > **Note**
      >
      > You can also maintain the information of an ordering party in this app by setting the **Object Type** field to **Business Partner**.

    - **Description**: Descriptive information about the location

    - **Source System/External ID**: Source system from which the location master data is copied and the corresponding ID.

        - If you are creating a location from scratch, set the **Source System** part to LBN, and set the **External ID** part to the location ID you previously prepared.

        - If you are importing a location from SAP Transportation Management (TM), set the **Source System** to the business system name of your TM system and set the **External ID** to the location ID in TM.

          For locations that have its object type set to "Business Partner", you can find the business system name of your TM system and the location ID in the SOAP request message sent to LBN. In this request, the *MessageHeader.SenderBusinessSystemID* attribute specifies the business system name and the internal ID of the sender (the *MessageHeader.SenderParty.InternalID* attribute) specifies the location ID.

          Alternatively, you can run transaction code *SLDCHECK* in TM to view the business system name.

- **Logical System**: You can also use the **Logical System** field to identify the system from which the location master data is replicated.

  This is a mandatory field if you want to use the location in SAP Business Network Global Track and Trace. The logical system ID you enter here must be the same one that you used when configuring the replication of location master data via the Data Replication Framework. For more information, see Replicating Locations from SAP S/4HANA via Data Replication Framework (DRF). Make sure you enter the logical system ID correctly so that it matches the source system of the location. Otherwise, there can be duplicate records in your location master data.

- (Optional) **Address**:
  - **Country/Region**
  - **State**
  - **City**
  - **District**
  - **Street/House Number**
  - **Zip Code**
- (Optional) **Geographical Coordinates And Map**:
  - **Longitude**: Longitude coordinate of the location
  - **Latitude**: Latitude coordinate of the location

  > **Note**
  >
  > You can enter the coordinates in the **Longitude** and **Latitude** fields manually. If you want the system to verify your entries, set **Calibrate coordinates when saving** to **Yes** before you save your changes. You can also choose **Generate Longitude and Latitude Coordinates** to create the coordinates according to the address information you've entered.
  >
  > By default, **Calibrate coordinates when saving** is set to **Apply global settings**, meaning that how the system handles coordinates for the location record you are working on is determined by the option you choose in the **Generate geo-coordinates automatically** setting, which can be found in the **Settings** dialogue box. If you leave **Generate geo-coordinates automatically** with the default option, the system generates geo-coordinates for locations when both the latitude and longitude coordinates are missing. For more information, see Global settings for Geo-Coordinates.

- (Optional) **Time Zone**
- (Optional) **Alternative Location ID**:
  - **Type**: Type of the alternative ID.
  - **ID**: Alternative ID in the specified type.
- (Optional) **Contact Information**: Contact information related to the location.
- (Optional) **Additional Information**: Additional information about the location. For more detail, see Define Additional Information.

3. Choose **Save**.

Result

The newly-created location master data can be consumed by other apps in SAP Business Network Global Track and Trace.

Upload Locations

You can fill the details of locations using an Excel template and then upload this template back to the app. To do this, follow these steps:

1. Choose **Upload** to open the **Upload Locations** page.
2. Click **Upload** on the up-right corner, then download the Excel template available by choosing **Download Excel Template**.
3. Fill the details of the locations you want to upload in the template.
4. In **Choose File**, locate the modified Excel template and then choose **Upload**.

ℹ Note

You can enter the geographical coordinates for the location records in the **Longitude** and **Latitude** columns manually. If you want the system to verify your entries, set **Calibrate coordinates when saving** to **Yes** before you upload your file.

By default, **Calibrate coordinates when saving** is set to **Apply global settings**, meaning that how the system handles coordinates for the location records you are uploading is determined by the option you choose in the **Generate geo-coordinates automatically** setting, which can be found in the **Settings** dialogue box. If you leave **Generate geo-coordinates automatically** with the default option, the system generates geo-coordinates for locations when both the latitude and longitude coordinates are missing. For more information, see Global settings for Geo-Coordinates.

Editing a Location

To edit a location, proceed as follows:

1. Use the following fields to filter locations:
    - Location ID
    - Description
    - Location Type
    - Country/Region
    - City
2. Click the location from the filter results to open the details page.
3. Choose **Edit** on the upper-right corner of the details page.

Enable Risk Monitoring

If you have configured the risk monitoring service provider in Configure Partner Connections, you can determine whether or not to use the service provider to monitor risks at a certain location in Manage Locations.

ℹ Note

Risk information is not displayed in Manage Locations. Instead, it's displayed on the map view of the Logistics Execution Insights app. You use Manage Locations to specify a group of target locations where you want to monitor risks.

Prerequisites

You have configured the risk monitoring service provider in Configure Partner Connections.

Procedure

To enable risk monitoring for a specific location, follow these steps:

1. Click the location record for which you want to monitor risks to open its details page.
2. Choose **Edit** on the upper-right corner.
3. Click to select the **Enable supply chain risk monitoring** checkbox and then choose **Save**.

Note

You can also configure this setting when creating a new location record.

Alternatively, you can enable risk monitoring for multiple locations at once. To do this, select the location records, and then choose **Risk Monitoring** > **Enable**.

Results

The risk monitoring service provider starts monitoring risks at the location. If you've subscribed for the intelligent insights add-on, you can view the risk information on each target location in the Logistics Execution Insights app.

To notify the service provider to stop monitoring risks at a location, uncheck the **Enable supply chain risk monitoring** checkbox in the corresponding location record.

To stop using the risk monitoring feature for all locations in your supply chain, uncheck the **Enable supply chain risk monitoring** checkbox in each location record where you previously enabled the feature in Manage Locations and then deactivate the risk monitoring service provider in Configure Partner Connections.

More Information

Editing a Location

Creating a Location

Manage Custom Codes

You can use the manage custom codes feature to extend the drop-down list for the following fields:

- Country/Region
- State
- Location Type

- Time Zone
- Role of Contact

This feature is useful if the drop-down list of a field does not contain the code you want to select. For example, you do not find the region code you need in the drop-down list of **Country/Region**.

To create a custom code, proceed as follows:

1. Choose the **Manage Custom Codes** button.
2. On the **Manage Custom Codes** page, select the field for which you want to extend the list, and then choose **Create**.
3. Specify the name, language, and description of the code, and then choose **Save**.

Results

After you create a custom code, you can find it from the **Custom** category when you expand the corresponding drop-down list. If needed, you can also remove it or edit its description on the **Manage Custom Codes** page.

Global settings for Geo-Coordinates

You can use **Generate geo-coordinates automatically** in the **Settings** dialogue box to define how the system handles geo-coordinates for all location records. In **Generate geo-coordinates automatically**, you have the following options:

- **Off** (Default): Do not generate geo-coordinates automatically even if they are missing.
- **Generate**: Generate geo-coordinates for locations when both the latitude and longitude coordinates are missing. (Applies to all locations including the existing ones)
- **Overwrite**: Generate geo-coordinates for locations when coordinates are missing or overwrite them if they already exist. (Applies to locations created after you enable this option)

ℹ Note

- Options in **Generate geo-coordinates automatically** only take effect for location records where you leave **Calibrate coordinates when saving** with the default option **Apply global settings**.
- The **Calibrate coordinates when saving** setting in location records takes precedence over **Generate geo-coordinates automatically** in the **Settings** dialogue box. For example, when you set **Calibrate coordinates when saving** to **No** in a location record, the system does not generate or calibrate coordinates for the record even if **Generate geo-coordinates** automatically is set to **Generate** or **Overwrite**.

Archiving Locations

If you have location records that are no longer used regularly, you can archive these records for future reference or regulatory compliance.

ℹ Note

To archive locations, you must have the LocationArchiveTemplate role.

To archive location records, select the records you want to archive on the **Locations** list and then choose **Archive**. You can view the locations you've archived on the **Archived Locations** list by choosing **Archived Items** at the up-right corner.

To restore archived location records, select the records you want to restore on the **Archived Locations** list, and then choose **Restore**. You can view the restored locations after you switch to the standard **Locations** list.

Define Additional Information

The Additional Information section contains a list of additional information associated to a location record. This section enables you to define necessary custom characteristics or references by adding your information items.

An information item comprises a name, the type of the item, and the corresponding value.

- **Type**: Type of the additional information item. It can be either **Text** or **Alternative ID**.
- **Name**: Name of the additional information item. If you set **Type** to **Alternative ID**, the name of the item must be set to one of the following values:
    - GLN
    - DUNS
    - UN/LOCODE
    - IATA Airport Code
- **Value**: Value that corresponds to this additional information item.

If you have a location that contains multiple ports or airports, you can maintain multiple UN/LOCODEs and IATA Airport Codes for this location in this section. But to ensure that the actual event matches with the correct planned/unplanned event, be aware of the following event match rules:

- For planned events, when multiple location records are found with the same UN/LOCODE or IATA Airport Code, the system will match the actual event with the planned event that has the same location alternative key.
- For unplanned events, the UN/LOCODE or IATA Airport Code maintained in the **Alternative Location IDs** section of the Manage Locations app is superior to the one maintained in the **Additional Information** section.

  For example, when two location records (A and B) are found with the same UN/LOCODE, but the UN/LOCODE in Location A is maintained in the **Alternative Location IDs** section and the UN/LOCODE in Location B is maintained in the **Additional Information** section, the system will take Location A as the superior one, and match the actual event with the unplanned event that has Location A.

Discover Business Partners

Finding the right business partners is always a challenge. However, this will be easier once your partners-to-be have joined SAP Business Network for Logistics.

As a simple yet powerful app in SAP Business Network for Logistics, **Discover Business Partners** helps you search the network for logistics service providers, then from the results, invite suitable ones to be your business partners.

Search for Business Partners

To search for business partners on the network, enter a key word, for example the company name, in the search box and then press Enter. You can also use faceted search on the left pane to narrow down your search results. When using faceted search, you can even leave the search box empty. This is useful if you want to explore your potential partners in a specific region or industry.

> **Note**
>
> If the business partners you are trying to connect with operates in a different data center, you must first ensure that your company profile is available across all data centers of SAP Business Network for Logistics. For more information, refer to Profile Settings.

Result

A set of matched results are returned. You can click to open the details page of a matched result.

> **Note**
>
> If the companies that match your search conditions are not found, see Discover Business Partners App and refer to "Why companies that match my search conditions are not returned in the Matched Results table?"

Send Request for Connection

To send a request for connection to your potential business partners, proceed as follows:

1. Click to select the company to which you want to send the request for connection from the **Matched Results** table.
2. Choose **Request for Connection**. The request for connection is sent to the selected companies.

Results

A request for connection is sent to the selected company. Once the company accepts your request, you will become business partners.

After you've set up a partnership with a business partner via this app, you must update the business partner's LBN ID in SAP Transportation Management (SAP TM). To do this, see Updating Business Partner's LBN ID.

References

Manage Business Profile

Manage Invitations

Updating Business Partner's LBN ID

To update the LBN ID in SAP Transportation Management (SAP TM) for a logistics service provider who's become your business partner, proceed as follows in SAP TM:

1. Go to the **Manage Business Partner** transaction (transaction BP).
2. Set the filter criteria to find the business partner for which you want to update the LBN ID and then double-click the business partner to open its **Display Organization** page.
3. Navigate to the **Identification** tab. In the **Identification Numbers** section, **IDType** field, enter `LBN001`.
4. In the **Identification Number** field, enter the LBN ID and save your changes.

Assign Technical User Roles to Data Contributor's Technical User

Prerequisites

You must have the administrator role for your subaccount on SAP BTP.

Context

If you are using SAP Business Network Global Track and Trace, your connected data contributor will send you the email address of its technical user after accepting your connection request. You need to grant the technical user the technical user roles. This needs to be performed for each data contributor that's connected with you.

Procedure

1. Go to your subaccount in the SAP BTP cockpit.
2. In the left-hand pane, choose **Role Collections** under **Security**.
3. Choose the technical user role collection (you've created it in the task Organize Roles Together and Assign Them to Users).

   > **Note**
   > Make sure the role collection contains all the technical user roles as listed in Available Roles for Solution Owners.

4. Go to the **Users** section and choose **Edit**.
5. Enter the email address of the technical user and select **Default identity provider**.
6. Save your changes.

Related Information

Assign Users to Role Collection

Template Apps (Deprecated)

Template, or sample, apps for Version 2 cover different business scenarios and are provided as code for you to customize for your own use. They:

- integrate with the Version 2 apps using the same look and feel
- can be customized to fit your own requirements, then deployed
- are available as sample code on GitHub.com from the following GTT repository in the SAP Samples organization: https://github.com/SAP-samples/logistics-business-network-gtt-samples

For more information, see the following files in the repository:

1. LICENSE
2. NOTICE
3. README.md

Track SO Fulfillment Template App

A template app for Version 2:

- for Internal Sales Representatives
- to track sales order fulfillment status with integration to SAP S/4HANA and a Visibility Provider

You can find documents explaining how to download and install the sample code for the template app from the GTT repository in the folder: ***lbn-gtt-template-tso***.

Track Shipments Template App

A template app for Version 2:

- for Transportation Planners (EM)
- to track the execution of shipments, road-related freight orders and ocean-related freight bookings

You can find documents explaining how to download and install the sample code for the template app from the GTT repository in the folder: ***lbn-gtt-template-ts***.

Track PO Fulfillment Template App

A template app for Version 2:

- for Purchasing Supervisors
- to track purchase order fulfillment status with integration to SAP S/4HANA and a Visibility Provider

You can find documents explaining how to download and install the sample code for the template app from the GTT repository in the folder: ***lbn-gtt-template-tpo***.

HERE Map Service Migration Guide

HERE Map Tile API is used by SAP Business Network Global Track and Trace to retrieve map tile images for creating a complete map in apps. As informed by HERE, the service has been upgraded to HERE Raster Tile API v3 (Click here for more information). To ensure that the map in **template apps** can work as usual, you must migrate to HERE Raster Tile API v3 manually in your deployed template apps by June 2024.

Prerequisite

You have implemented the following template apps with the codes provided in the GitHub repository: https://github.com/SAP-samples/logistics-business-network-gtt-samples :

- Track Shipments app
- Track SO Fulfillment app
- Track PO Fulfillment app

The migration steps for these three template apps are listed separately in the sections followed.

Track Shipments App

To migrate to the HERE Raster Tile API v3 service, do the following:

1. Open the file "**MapHelper.js**" under **lbn-gtt-template-ts** > **GTT-V2-Sample-TrackShipments-UI** > **ui** > **weapp** > **controller** in the repository.
2. Overwrite the function "**MapHelper.setMapConfiguration**" with the sample codes attached at the end of this section.
3. Deploy the app. For more information on deployment, see 02_Implementation_Guide-TS.pdf under the **Documents** folder.

Sample Code

```
MapHelper.setMapConfiguration = function (map, provider) {
      var protocal = "https";
      var hereHost1 = "maps.hereapi.com";
      var appLanguage = sap.ui.getCore().getConfiguration().getLanguageTag().slice(0, 2);
      var servicePattern =
        "{0}://{1}/v3/base/mc/'{LOD}'/'{X}'/'{Y}'/png8?apiKey={2}&lang={3}&lang2=en";

      var configuration = {
        "MapProvider": [{
          "name": "HERE",
          "type": "",
          "description": "",
          "tileX": "256",
          "tileY": "256",
          "maxLOD": "22",
          "copyright": "Copyright &copy; HERE",
          "Source": [hereHost1].map(function (hereHost, index) {
            return {
              "id": "server" + index,
              "url": formatMessage(servicePattern, protocal, hereHost, keys.HERE, appLanguage),
            };
          }),
        }, {
          "name": "OpenStreet",
          "type": "",
          "description": "",
          "tileX": "256",
          "tileY": "256",
          "maxLOD": "22",
          "copyright": "Copyright &copy; OpenStreet",
          "Source": [{
            "id": "s1",
            "url": formatMessage("{0}://maps.geoapify.com/v1/tile/osm-carto/'{LOD}'/'{X}'/'{Y}'.
          }],
        }],
        "MapLayerStacks": [{
          "name": "DEFAULT",
          "MapLayer": {
            "name": "layer1",
            "refMapProvider": provider || "OpenStreet",
            "opacity": "1.0",
            "colBkgnd": "RGB(255,255,255)",
          },
        }],
      };
      map.setMapConfiguration(configuration);
      map.setRefMapLayerStack("DEFAULT");
};
```

Track SO Fulfillment App

To migrate to the HERE Raster Tile API v3 service, do the following:

1. Open the file "**MapHelper.js**" under **lbn-gtt-template-tso** > **GTT-V2-Sample-TrackSalesOrders-UI** > **ui** > **webapp** > **controller** in the repository.