	Selected Values **Code** BAG **Name** Bag **Code** BAL **Name** Bale **Code** BLK **Name** Bulk **Code** BDL **Name** Bundle **Code** BOT **Name** Bottle **Code** BRG **Name** Barge **Code** CAN **Name** Can **Code** CBY **Name** Carboy **Code** CAS **Name** Case **Code** CRT **Name** Crate **Code** COL **Name** Coil **Code** CNT **Name** Container **Code** CYL **Name** Cylinder **Code** CTN **Name** Carton **Code** DRM **Name** Drum **Code** JAR **Name** Jar **Code** PCS **Name** Pieces **Code** PKG **Name** Package **Code** PLT **Name** Pallet **Code** PCK **Name** Packed - not otherwise specified **Code** SPL **Name** Spool **Code** SHT **Name** Sheet A thin layer of material usually used as a pad for extra protection by isolating/separating tiers or layers of parts within the package **Code** TBN **Name** Tote Bin **Code** TBE **Name** Tube **Code** TLD **Name** Intermodal Trailer/Container Load (Rail)	**Data Type** AN **Position** 05 **Codelist Id** 103 **Type System** ASC_X12 **Version Mode** Current **Version** 004010

4.25 AT8 — Shipment Weight, Packaging and Quantity Data

Structure

Node	Card.	Prim.Type	Pos.	Length	Codelists
204 — Motor Carrier Load Tender	1 .. 1				
├ **0300** — Loop 0300 - Complete or Others	2 .. 999		010		
│ └ **0350** — Loop 0350	0 .. 999		150		
│ └ **0360** — Loop 0360	0 .. 99		190		
│ ├ **AT8** — Shipment Weight, Packaging and Quantity Data	0 .. 1		195		
│ │ ├ **187** — Weight Qualifier	0 .. 1	Token	01	1 .. 2	187
│ │ ├ **188** — Weight Unit Code	0 .. 1	Token	02	1 .. 1	188
│ │ ├ **81** — Weight	0 .. 1	Decimal	03	1 .. 10	
│ │ ├ **80** — Lading Quantity	0 .. 1	Integer	04	1 .. 7	
│ │ ├ **184** — Volume Unit Qualifier	0 .. 1	Token	06	1 .. 1	184
│ │ └ **183** — Volume	0 .. 1	Decimal	07	1 .. 8	

Documentation

Definition To specify shipment details in terms of weight, and quantity of handling units

Properties

Identifier AT8

Name Shipment Weight, Packaging and Quantity Data

Cardinality min: 0 max: 1

Syntax Type Related

External Category Segment

Position 195

Level 5

Notes

Usage 1 AT804 is the quantity of handling units that are not unitized (for example a carton).

Constraint 1 P010203 Paired Multiple - If any are used, all must be used

Constraint 2 P0607 Paired Multiple - If any are used, all must be used

Leaf Elements

Identifier/Name	Description/Notes/Code Values	Properties
187 Weight Qualifier	Code defining the type of weight **Selected Values** All Values in Codelist	**Cardinality** min: 0 max: 1 **Primitive Type** Token **Length** min: 1 max: 2 **External Category** Simple Data Element **Data Type** ID **Position** 01 **Codelist Id** 187 **Type System** ASC_X12 **Version Mode** Current **Version** 004010
188 Weight Unit Code	Code specifying the weight unit **Selected Values** **Code E Name** Metric Ton **Code G Name** Grams **Code K Name** Kilograms **Code L Name** Pounds **Code O Name** Ounces **Code S Name** Short Ton **Code T Name** Long Ton	**Cardinality** min: 0 max: 1 **Primitive Type** Token **Length** min: 1 max: 1 **External Category** Simple Data Element **Data Type** ID **Position** 02 **Codelist Id** 188 **Type System** ASC_X12 **Version Mode** Current

		Version 004010
81 Weight	Numeric value of weight	**Cardinality** **min:** 0 **max:** 1 **Primitive Type** Decimal **Length** **min:** 1 **max:** 10 **Total Digits** 10 **External Category** Simple Data Element **Data Type** R **Position** 03
80 Lading Quantity	Number of units (pieces) of the lading commodity	**Cardinality** **min:** 0 **max:** 1 **Primitive Type** Integer **Length** **min:** 1 **max:** 7 **Fraction Digits** 0 **Total Digits** 7 **External Category** Simple Data Element **Data Type** N0 **Position** 04
184 Volume Unit Qualifier	Code identifying the volume unit **Selected Values** **Code** B **Name** Barge **Code** C **Name** Cubic Centimeters **Code** D **Name** Cord **Code** E **Name** Cubic Feet **Code** G **Name** Gallons **Code** L **Name** Load **Code** M **Name** Cubic Decimeters **Code** N **Name** Cubic Inches **Code** R **Name** Car **Code** T **Name** Container **Code** V **Name** Liter **Code** X **Name** Cubic Meters	**Cardinality** **min:** 0 **max:** 1 **Primitive Type** Token **Length** **min:** 1 **max:** 1 **External Category** Simple Data Element **Data Type** ID **Position** 06 **Codelist Id** 184 **Type System** ASC_X12 **Version Mode** Current **Version** 004010
183 Volume	Value of volumetric measure	**Cardinality** **min:** 0 **max:** 1 **Primitive Type** Decimal **Length** **min:** 1 **max:** 8 **Total Digits** 8 **External Category** Simple Data Element **Data Type** R **Position** 07

4.26 0365 — Loop 0365

Structure

Node	Card.	Prim.Type	Pos.	Length	Codelists
204 — Motor Carrier Load Tender	1 .. 1				
├ **0300** — Loop 0300 - Complete or Others	2 .. 999		010		
│ └ **0350** — Loop 0350	0 .. 999		150		
│ └ **0360** — Loop 0360	0 .. 99		190		
│ └ **0365** — Loop 0365	0 .. 99		200		
│ ├ **G61** — Contact	1 .. 1		200		
│ └ **0370** — Loop 0370	0 .. 25		203		

Properties

Identifier 0365

Name Loop 0365

Cardinality min: 0 max: 99

Syntax Type Related

External Category Loop

Position 200

Level 5

4.27 G61 — Contact

Structure

Node	Card.	Prim.Type	Pos.	Length	Codelists
204 — Motor Carrier Load Tender	1 .. 1				
├ **0300** — Loop 0300 - Complete or Others	2 .. 999		010		
│ └ **0350** — Loop 0350	0 .. 999		150		
│ └ **0360** — Loop 0360	0 .. 99		190		
│ └ **0365** — Loop 0365	0 .. 99		200		
│ ├ **G61** — Contact	1 .. 1		200		
│ │ ├ **366** — Contact Function Code	1 .. 1	Token	01	2 .. 2	366
│ │ └ **93** — Name	1 .. 1	String	02	1 .. 60	

Documentation

Definition To identify a person or office to whom communications should be directed

Properties

Identifier G61

Name Contact

Cardinality min: 1 max: 1

Syntax Type Related

External Category Segment

Position 200

Level 6

Notes

Constraint 1 P0304 Paired Multiple - If any are used, all must be used

Comment 1 G6103 qualifies G6104.

Leaf Elements

Identifier/Name	Description/Notes/Code Values	Properties
366 Contact Function Code	Code identifying the major duty or responsibility of the person or group named **Selected Values** **Code** SH **Name** Shipper Contact	**Cardinality** min: 1 max: 1 **Primitive Type** Token **Length** min: 2 max: 2 **External Category** Simple Data Element **Data Type** ID **Position** 01 **Fixed Value** SH **Codelist Id** 366 **Type System** ASC_X12 **Version Mode** Current **Version** 004010
93 Name	Free-form name	**Cardinality** min: 1 max: 1 **Primitive Type** String **Length** min: 1 max: 60 **External Category** Simple Data Element **Data Type** AN **Position** 02

4.28 0370 — Loop 0370

Structure

Node	Card.	Prim.Type	Pos.	Length	Codelists
204 — Motor Carrier Load Tender	1 .. 1				
├ **0300** — Loop 0300 - Complete or Others	2 .. 999		010		
│ └ **0350** — Loop 0350	0 .. 999		150		
│ └ **0360** — Loop 0360	0 .. 99		190		
│ └ **0365** — Loop 0365	0 .. 99		200		
│ └ **0370** — Loop 0370	0 .. 25		203		
│ ├ **LH1** — Hazardous Identification Information	1 .. 1		203		
│ ├ **LH2** — Hazardous Classification Information	0 .. 4		204		
│ └ **LFH** — Freeform Hazardous Material Information	0 .. 20		206		

Properties

Identifier 0370

Name Loop 0370

Cardinality min: 0 max: 25

Syntax Type Related

External Category Loop

Position 203

Level 6

4.29 LH1 — Hazardous Identification Information

Structure

Node	Card.	Prim.Type	Pos.	Length	Codelists
204 — Motor Carrier Load Tender	1 .. 1				
├ **0300** — Loop 0300 - Complete or Others	2 .. 999		010		
│ └ **0350** — Loop 0350	0 .. 999		150		
│ └ **0360** — Loop 0360	0 .. 99		190		
│ └ **0365** — Loop 0365	0 .. 99		200		
│ └ **0370** — Loop 0370	0 .. 25		203		
│ ├ **LH1** — Hazardous Identification Information	1 .. 1		203		
│ ├ **355** — Unit or Basis for Measurement Code	1 .. 1	Token	01	2 .. 2	355
│ ├ **80** — Lading Quantity	1 .. 1	Integer	02	1 .. 7	
│ ├ **277** — UN/NA Identification Code	0 .. 1	Token	03	6 .. 6	
│ └ **254** — Packing Group Code	0 .. 1	Token	10	1 .. 3	

Documentation

Definition To specify the hazardous commodity identification reference number and quantity

Properties

Identifier LH1

Name Hazardous Identification Information

Cardinality min: 1 max: 1

Syntax Type Related

External Category Segment

Position 203

Level 7

Notes

Comment 1 LH101 and LH102 are used to convey the number and type of packages for bulk and nonbulk movements.

Comment 2 LH106 and LH107 are used to convey the quantity or volume and unit of measure for nonbulk shipments only.

Comment 3 In LH109, a value of “R” or “P” requires that the receiver generate the words “residue: last contained” prior to the shipping name in accordance with regulations.

Leaf Elements

Identifier/Name	Description/Notes/Code Values	Properties
355 Unit or Basis for Measurement Code	Code specifying the units in which a value is being expressed, or manner in which a measurement has been taken **Selected Values** **Code** B8 **Name** Board **Code** BI **Name** Bar A centimeter-gram-second unit of pressure, equal to one million dynes per square centimeter **Code** BO **Name** Bottle **Code** BD **Name** Bundle **Code** BG **Name** Bag **Code** BC **Name** Bucket **Code** BA **Name** Bale **Code** BU **Name** Bushel 32 dry quarts **Code** CP **Name** Crate	**Cardinality** min: 1 max: 1 **Primitive Type** Token **Length** min: 2 max: 2 **External Category** Simple Data Element **Data Type** ID **Position** 01 **Codelist Id** 355 **Type System** ASC_X12 **Version Mode** Current **Version** 004010

	Code CN **Name** Can **Code** CH **Name** Container **Code** CX **Name** Coil **Code** CB **Name** Carboy **Code** CQ **Name** Cartridge **Code** CA **Name** Case **Code** CS **Name** Cassette **Code** CT **Name** Carton **Code** CL **Name** Cylinder **Code** DC **Name** Disk (Disc) **Code** DR **Name** Drum **Code** DZ **Name** Dozen **Code** NT **Name** Trailer **Code** EA **Name** Each **Code** PC **Name** Piece **Code** JR **Name** Jar **Code** NB **Name** Barge **Code** PK **Name** Package **Code** PL **Name** Pallet/Unit Load **Code** PH **Name** Pack (PAK) **Code** PA **Name** Pail **Code** PR **Name** Pair **Code** SO **Name** Spool **Code** SH **Name** Sheet **Code** TE **Name** Tote **Code** TB **Name** Tube **Code** BN **Name** Bulk **Code** UL **Name** Unitless Unit of Measure for properties or test results without units of measure	
80 Lading Quantity	Number of units (pieces) of the lading commodity	**Cardinality** **min:** 1 **max:** 1 **Primitive Type** Integer **Length** **min:** 1 **max:** 7 **Fraction Digits** 0 **Total Digits** 7 **External Category** Simple Data Element **Data Type** N0 **Position** 02
277 UN/NA Identification Code	Code identifying the hazardous material identification number as required by Title 49 of the code of Federal Regulations; UN/NA stands for United Nations/North America	**Cardinality** **min:** 0 **max:** 1 **Primitive Type** Token **Length** **min:** 6 **max:** 6 **External Category** Simple Data Element **Data Type** ID **Position** 03
254 Packing Group Code	Code indicating degree of danger in terms of Roman number I, II or III	**Cardinality** **min:** 0 **max:** 1 **Primitive Type** Token **Length** **min:** 1 **max:** 3 **External Category** Simple Data Element **Data Type** ID **Position** 10

4.30 LH2 — Hazardous Classification Information

Structure

Node	Card.	Prim.Type	Pos.	Length	Codelists
204 — Motor Carrier Load Tender	1 .. 1				
├ **0300** — Loop 0300 - Complete or Others	2 .. 999		010		
│ └ **0350** — Loop 0350	0 .. 999		150		
│ └ **0360** — Loop 0360	0 .. 99		190		
│ └ **0365** — Loop 0365	0 .. 99		200		
│ └ **0370** — Loop 0370	0 .. 25		203		
│ ├ **LH2** — Hazardous Classification Information	0 .. 4		204		
│ │ ├ **215** — Hazardous Classification	0 .. 1	Token	01	1 .. 30	
│ │ ├ **983** — Hazardous Class Qualifier	0 .. 1	Token	02	1 .. 1	983
│ │ ├ **355** — Unit or Basis for Measurement Code	0 .. 1	Token	06	2 .. 2	355
│ │ └ **408** — Temperature	0 .. 1	Decimal	07	1 .. 4	

Documentation

Definition To specify the hazardous notation and endorsement information

Properties

Identifier LH2

Name Hazardous Classification Information

Cardinality min: 0 max: 4

Syntax Type Related

External Category Segment

Position 204

Level 7

Notes

Usage 1 LH206 and LH207 indicate the flashpoint temperature.

Usage 2 LH208 and LH209 indicate the control temperature.

Usage 3 LH210 and LH211 indicate the emergency temperature.

Constraint 1 P0607 Paired Multiple - If any are used, all must be used

Constraint 2 P0809 Paired Multiple - If any are used, all must be used

Constraint 3 P1011 Paired Multiple - If any are used, all must be used

Leaf Elements

Identifier/Name	Description/Notes/Code Values	Properties
215 Hazardous Classification	The hazardous classification corresponding to the shipping name of the hazardous commodity	**Cardinality** min: 0 max: 1 **Primitive Type** Token **Length** min: 1 max: 30 **External Category** Simple Data Element **Data Type** ID **Position** 01
983 Hazardous Class Qualifier	Code qualifying hazardous class **Selected Values** All Values in Codelist	**Cardinality** min: 0 max: 1 **Primitive Type** Token **Length** min: 1 max: 1 **External Category** Simple Data Element **Data Type** ID **Position** 02 **Codelist Id** 983 **Type System** ASC_X12

		Version Mode Current **Version** 004010
355 Unit or Basis for Measurement Code	Code specifying the units in which a value is being expressed, or manner in which a measurement has been taken **Selected Values** All Values in Codelist	**Cardinality** **min:** 0 **max:** 1 **Primitive Type** Token **Length** **min:** 2 **max:** 2 **External Category** Simple Data Element **Data Type** ID **Position** 06 **Codelist Id** 355 **Type System** ASC_X12 **Version Mode** Current **Version** 004010
408 Temperature	Temperature	**Cardinality** **min:** 0 **max:** 1 **Primitive Type** Decimal **Length** **min:** 1 **max:** 4 **Total Digits** 4 **External Category** Simple Data Element **Data Type** R **Position** 07