More Tasks

On the top right of **Model Details** page, there is an Additional Options icon ••• that contains the following actions:

- Activate/Deactivate the Model
- Delete Business Data of the Model
- Export Business Data of the Model
- Enable/Disable the Model Cache
- Enable/Disable Event to Action Log of the Model
- View the Model History

Activate/Deactivate the Model

Context

When a model is deployed, you can activate/deactivate the model to expose/conceal the Write Service and Read Service APIs for consumption.

Procedure

1. Launch the MM app. Select a deployed model.
2. On the **Model Details** page, switch to the **Runtime** or **Deployed** view.
3. Click the **Additional Options** icon ••• and select:
    - **Activate**: to expose the API for consumption
    - **Deactivate**: not to expose the API for consumption.
4. Click **OK** in the confirmation box.
5. The deployed version of the model is then active/inactive.
    - If it's active, you can read the model metadata and business data, and write the business data.
    - If it's inactive, you can only read the model metadata.

Delete Business Data of the Model

Context

When a model is deployed, you can delete the business data of the logical system you specified, including the tracked processes with corresponding events.

Procedure

1. Launch the MM app. Select a deployed model.
2. On the **Model Details** page, switch to the **Runtime** or **Deployed** view.
3. Click the **Additional Options** icon ••• and select **Delete Business Data**.

4. Select **All** or **Specified Logical System**. If you choose the latter, enter the logical system name.
5. Click **Delete**.

Export Business Data of the Model

Context

When a model is deployed, you can export the business data of the model, including the tracked processes with corresponding events, and download the files in the ZIP format.

To use this function, you must have the `DataModelAdminTemplate` role to your role collection. For more, see the Available Roles for Solution Owners section in the *Administration Guide for Solution Owners*.

Procedure

1. Launch the MM app. Select a deployed model.
2. On the **Model Details** page, switch to the **Runtime** or **Deployed** view.
3. Click the **Additional Options** icon ••• and select **Export Business Data**.
4. In the pop-up, select a time type that you want the time range of your exported business data to be based on:
    - the **Last Changed Time** of tracked processes
    - or the **Creation Time** of tracked processes.
5. Specify the time range for the data you want to export with the **Start Time** and **End Time** filters. The duration between the start time and the end time cannot exceed 365 days.
6. Select the tracked process(es) that you want to export. If you don't select any, all tracked processes will be exported.
7. Click **Request Export**. A confirmation box pops up. Click **OK** to confirm. A request is then generated under the **Requests** table. The following columns are displayed:
    - **Exported File**: displays the request and the file that is exported within this request. Each request is named after the date and time when it is created. You can click ⓘ after each request to see the time type, time range and tracked processes you previously specified. If no tracked process is selected in the last step, the **Tracked Process** field in the pop-over is left empty. But it indicates that all tracked processes are exported.

      Once the request is completed, expand the request and you can see a list of exported files in the ZIP format that you can download. Each file represents a tracked process and its events. The maximum file size is 100 MB. If the data for a tracked process exceeds this limit, a new file will be created.
    - **Completed Time**: shows when the request is completed.
    - **Status**: shows the processing progress of the request:
        - The progress icon ⋙ means the request is being processed.
        - The completion icon ✓ means the request is successfully processed.
        - The warning icon ⚠ means the request fails to be processed. You must generate a new export request.

    Note

    The requests will be automatically deleted after 7 days. If the number of requests exceeds 10, only the latest 10 requests are kept.

8. When the request is completed, select a file that you want to download.

9. Click **Download**. The file will then be saved to your local device. When you extract the file, you'll see a collection of JSON files in the resulting folder.

Enable/Disable the Model Cache

Context

When a model is deployed, you can enable/disable the model cache. The default is Enabled. If you change the model cache switch from Enabled to Disabled or from Disabled to Enabled, the change needs at most 15 minutes to take effect.

⚠ Caution

In production tenants, enabling the model cache is strongly recommended to ensure optimal message processing performance. Disabling the model cache in production tenants significantly slows down the message processing and could lead to a great number of pending messages in the Manage Message Logs app.

ℹ Note

This also applies to the Configure Partner Connections API cache. By default, the cache is enabled when calling Configure Partner Connections API internally. When you enable/disable the model cache, the Configure Partner Connections API cache is enabled/disabled at the same time.

Procedure

1. Launch the MM app. Select a deployed model.
2. On the **Model Details** page, switch to the **Runtime** or **Deployed** view.
3. Click the **Additional Options** icon ••• and select **Enable/Disable Model Cache**.
4. Click **OK** in the confirmation box.
5. The model cache is then enabled/disabled.
    - If it is **Enabled**, when you make any changes to the model and redeploy it, the model cache in the runtime needs at most 15 minutes to expire. New changes will take effect thereafter. The same applies to the Configure Partner Connections app.
    - If it is **Disabled**, when you make any changes to the model and redeploy it, new changes will take effect at once. The same applies to the Configure Partner Connections app.

Enable/Disable Event to Action Log of the Model

Context

When a model is deployed, you can enable/disable the logging of certain items related to your event-to-action script. These items are recorded in message logs and event logs. They include:

- the Event to Action Log statements
- the payload sent to the tracking API through the function `sendTrackingRequest`
- the payload sent to SAP Transportation Management through the function `forwardEventToTM`.

The default is **Disabled**/**Off**.

Once enabled, the system will start logging the above-mentioned items within 15 minutes. You can see the logs on the **Correlation Details** page of the Manage Message Logs app and the Manage Event Logs app. For instructions, see View Correlation Payload and Logs.

Procedure

1. Launch the MM app. Select a deployed model.
2. On the **Model Details** page, switch to the **Runtime** or **Deployed** view.
3. Click the **Additional Options** icon ••• and select **Enable/Disable Event to Action Log**.
4. Click **OK** in the confirmation box.
5. The Event to Action Log is then enabled/disabled.

View the Model History

Context

When a model is deleted, deployed, activated/deactivated, or meets deployment/deletion error, you can see the history details about the model.

Procedure

1. On the **Model Details** page, click the **Additional Options** icon ••• and select **History**.
2. The history log is displayed in chronological descending order by the action time.
3. The history log entries are grouped by weeks. Click the group title to collapse/expand the group.
4. The history log entry contains the information of the administrator who performed the action, action time and description.

Check Processes and Events

Check Processes and Events (CPE) displays a tracked process with its event data based on a deployed GTT metadata model. The app

- is used to display all the tracked processes that have been deployed, to test the models, and to check the data
- displays details of all its events for a selected tracked process
- displays the data for standard and user-defined fields in the model.

When you launch the CPE app, the overview page is displayed that lists all active process types with high-level information about each. Click a specific process type to see its data details on the **Process List** page.

Help and Support

There are several ways you can find help and support on the Fiori launchpad of SAP Business Network Global Track and Trace.

Built-In Support

Built-in support provides efficient, simplified and guided support channels, you can search for knowledge, ask for needed information, get help from recommended solutions. Currently, expert chat is not supported.

To access the built-in support service on the Fiori Launchpad, click the icon on the right corner of the screen. You will see a welcome page where you can sign in, and a list of recommended links for the page.

To gain full access to the built-in functions, you must activate your S-user. For more, see Activating Built-In Support Services.

For more information on how to use this tool, refer to Built-In Support on SAP Help Portal.

In-app Help

When you launch the app, you can turn on the in-app help that provides on-screen explanations of key fields and areas on the screen.

To turn on the in-app help, on the top right on the screen, click the icon.

Once the in-app help is turned on, you can:

- search the displayed help topics for the text that you type;
- click the icon to see the help texts on that topic;
- click the link tiles to see the documentation of this app on SAP Help Portal;
- hide the **Help Topics** panel by clicking the button on the bottom right.

Filters

You can apply one or more filters to reduce the number of process types displayed. You can also use value proposal search in selected filters. When you start typing, matching elements are displayed, and you can select them.

By default, the following filters are shown:

- **Process Type**: the type of a tracked process.
- **Model Namespace**: the full unique technical name of the model.
- **Last Deployed At**: the range of start to end date that the model was last deployed.

When you have completed your filter selection, click **Go**.

You have the following options to alter how filters are displayed:

- You can hide the filters by clicking the icon.
- You can pin the filters to the top of the screen by clicking the pin icon.

You can change the default filters, by clicking the **Adapt Filters** button.

Views

You can select a view, also called a variant. The view determines the number of process types listed on the overview page. There are two types, either:

- Standard: unfiltered so displays all active process types or
- one of the customized variants, if any have been created. These include some filters that may reduce the number of process types displayed.

After you select your view, its name is displayed on-screen. Click Go to display the corresponding process types.

An asterisk (*) is displayed after the view name whenever any additional filter selection(s) is made. You can save your selection to create your own view.

To create your own view:

- Click Adapt Filters and the Settings icon to personalize your filter and table settings respectively.
- Click the drop-down icon ⌄ to the right of the Standard view.
- Click Save As in the view selector.
- Enter a name for your view (case sensitive).
- You can also choose Set as Default and Apply Automatically.
- Save your view.

You can click Manage in the view selector to change the view settings.

Process List

From the overview page, click a specific process type to see data details of that process type on the Process List page.

By default, these filters are displayed:

- Alternative Key: the unique identifier of the tracked process in SAP Business Network for Logistics. It follows the pattern: ***scheme:party:system:type:id***
  - Scheme: “xri://sap.com/id”, a fixed value
  - Party: LBN ID of the business partner
  - System: name of the logical system that the tracked process comes from
  - Type: business or document type of the tracked process
  - ID: tracking ID of the tracked process
- Tracking ID: the document number of the tracked process
- Logical System: an application system in which the applications are coordinated to work in one common database, and from which the tracked process comes from
- Lifecycle Status: the lifecycle status of the tracked process. Select from the drop-down list one or more of:
  - Business Active: the default value when a tracked process is created. It indicates that the relevant data of the tracked process is used in the ongoing business.
  - End of Business: defines the end of active business and the start of residence time and retention period. When one of the last planned events is reported, the lifecycle status of the tracked process changes to “End of Business” automatically.

- **Process Status**: the actual status of a tracked process, decided by the status of the last planned event whose status is not “As Planned”. Select from the drop-down list one or more of:
    - **As Planned**: the initial status of a tracked process, also the status when the last planned event whose status is not “As Planned” is reported on time.
    - **Delayed**: the status when the last planned event whose status is not “As Planned” is expected to be late.
    - **Early**: the status when the last planned event whose status is not “As Planned” is early reported.
    - **Late**: the status when the last planned event whose status is not “As Planned” is late reported.
    - **Overdue**: the status when the last planned event whose status is not “As Planned” is overdue. Overdue indicates that the current timestamp exceeds the latest planned technical timestamp.

You can use the value proposal search in selected filters by clicking the icon . The case insensitive search is supported for the following conditions:

- “contains”
- “starts with”
- “ends with”.

When you start typing, matching elements are displayed, and you can select them.

To change the default filters, click **Adapt Filters**. More filters are provided, such as:

- **Estimated Status**: the estimated status of a tracked process, decided by the estimated status of the last unreported planned event whose status is not unknown. For details, see Important Terms.
- **ID**: the technical key of a tracked process.
- **Party ID**: the LBN ID of a solution owner or a data contributor.
- **Tracking ID Type**: the equivalent to the tracked process type.

In the table of **Processes**, you can change the default columns with the Settings icon to display the **View Settings** screen.

Select a process to go to the next page: **Process Details**.

Process Details

On the **Process Details** page, the following tabs are displayed:

Information

You may see the following selectable parts in this tab:

- **Core**: core information that is predefined by the GTT system in the model. To see more information, clickShow More. After that, click Show Less to hide the extra information.
- **Standard**: standard information that is predefined in the GTT standard model.
- User-defined: defined by the user in the model
- **Tracking IDs**: core composition with table type that is predefined by the GTT system in the model. You can change the default columns and sorting with the Settings icon. You can drill down further for more information.

- External Tracking IDs: core composition with table type that is predefined by the GTT system in the model. You can change the default columns and sorting with the Settings icon. You can drill down further for more information.
- One-Time Locations: core composition with table type that is predefined by the GTT system in the model. You can change the default columns and sorting with the Settings icon. You can drill down further for more information.

  You can use one-time locations for planned events without maintaining the locations in the Manage Locations app. Location geo coordinates will be automatically calculated based on the one-time location information provided, if they're not maintained.

  > **Note**
  >
  > The field "timeZone" supports the time zone IDs that are defined by IANA Time Zone Database. When setting values for the "timeZone" and "timeZoneId" fields, you should only provide a value for one of them. If you maintain the value of the parameter `GTT_OTL_TIMEZONE` in the `Tracked Process EM IDOC`, it will be automatically converted to the corresponding time zone ID. For more information on the mentioned IDOC, see IDOC Service.

- Standard Composition Names: table-typed fields predefined in the GTT standard model.
- User-defined Composition Names: table-typed fields defined by the user in the model. You can change the default columns and sorting with the Settings button. You can drill down further for more information.

Planned Events

The Planned Events table displays all the planned event data for the process in multiple columns including ID, Event Type, Location Alternative Key, Event Match Key, Event Status, Planned Business Timestamp, and Actual Business Timestamp.

> **Note**
>
> The "Actual Business Timestamp" is for the planned event's ***last correlated event****.

****last correlated event***: When an actual event is matched with a planned event successfully and the status of this planned event is calculated based on this actual event, then this actual event is considered as the last correlated event of this planned event.

You can change the default columns and sorting with the Settings icon. You can also drill down further for more information.

Other Events

Other events include:

- `GTTUpdatePlanEvent`
- Unplanned events: display all the actual event data that has been reported without any reference to a planned event.

You can change the default columns and sorting with the Settings icon. You can also drill down further for more information.

Attachments

This tab is displayed only when you create a user model field with its type as "Attachments" in the Tracked Process tab of the MM app.

A Refresh button is displayed on the top right. Click the button to update the data shown.

Planned Event Details

On the ***Process Details*** page, select a planned event from the ***Planned Events*** table to see the ***Planned Event Details*** page.

There are two tabs:

- **Planned Data**: It covers the information about the planned event including the core fields, standard fields and the user-defined fields.
- **Actual Data**: Only displayed if an actual event is reported with reference to this planned event. The information is held in a table. You can change the default columns and sorting with the Settings icon. Select an event to see the **Event Details** page.

A **Refresh** button is displayed on the top right. Click the button to update the data shown.

Event Details

On the **Process Details** page, select an event from the **Other Events** table to see the **Event Details** page. You can also see this page when you select an event from the **Actual Data** table on the **Planned Event Details** page.

The following tabs are displayed:

- **Information**: with details for the core fields, standard fields, and the user-defined fields.
- **References**: displayed in a table with columns such as ID, Event ID, and Reference Type. You can change the default columns and sorting with the Settings icon. You can also drill down further for more information.
- **Event Processes**: displayed in a table with columns such as Process, Planned Event Location Alternative Key, and Correlation Type. You can change the default columns and sorting with the Settings icon. You can click the link to a process in a row to see its **Process Details** page. You can also drill down further for more information.
- **Estimated Timestamps**: displayed in a table with columns such as ***ID, Event ID, Event Type, Location Alternative Key, Event Match Key*** and ***Estimated Timestamp.*** You can change the default columns and sorting with the Settings button.
- Standard Composition Names: table-typed fields predefined in the GTT standard model.
- User-defined Composition Names: table-typed fields defined by the user in the model. The information is displayed in a table with columns such as Stop ID, Planned Arrival At, and Location Time Zone. You can change the default columns and sorting with the Settings icon. You can also drill down further for more information.

Check Active Process Types

Context

To check the process types in all active models, do the following:

Procedure

1. Launch the CPE app.
2. The overview page displays the list of process types for all the active models.
3. As previously explained, you can reduce the number of process types displayed by setting one or more filters or using a view.

Related Information

Filters
Views

Check Active Processes

Context

To check active processes, do the following:

Procedure

1. Launch the CPE app.
2. The overview page displays the list of process types for all the active models.
3. Select a process type from the list and click it.
4. The **Process List** page displays a table of all active processes.

Related Information

Process List

View Tracked Process Details

Context

To view the details of a tracked process, do the following:

Procedure

1. Launch the CPE app.
2. The overview page displays the list of process types for all the active models.
3. Select a process type from the list and click it.
4. The **Process List** page displays a table of all active processes.
5. Select a process from the list and click it.
6. The **Process Details** page shows the information of the selected process arranged by:
    - **Information**
    - **Planned Events**
    - **Other Events**

Related Information

Process Details