- **Reference Document**

  You can view the following:

  - Customer purchase order details
  - Document ID and document type of the SAP Enterprise Resource Planning (SAP ERP) reference documents such as inbound delivery, outbound delivery, sales order, and purchase order document associated in the SAP Transportation Management system.

- **Other Details**

  Displays the following:

  - Over-Dimensional

    Displays whether the cargo item is over-dimensional

  - Non-Stackable
  - High Value

Execution Documents

The **Execution Documents** section displays the associated yard and the docking location. When you expand the docking location details, you can view the associated appointments. You can navigate to the appointment in **Manage Dock Appointments** app by choosing the appointment. The system displays the following appointment information in a card format:

- **Reference Document**
- **Dangerous Goods** indicator
- **Incoterm**

  Displays the Incoterm code.

  You can find the list of standard Incoterm codes supported by SAP Business Network for Logistics here: Incoterm Descriptions.

  Note that the system displays this field only if the ordering party has maintained this information in their external system.

- **Incoterm Location**

  Displays the location in SAP Business Network for Logistics or the incoterm location retrieved from the external system.

  - If the location is maintained in SAP Business Network for Logistics, the system tries to retrieve the description from the **Manage Locations** app under **Location Details** > **Description**.
  - If the location is not maintained in the **Manage Locations** app, the system displays the Incoterm location description retrieved from the external system (for example, TM).
  - **Exception**: In the **Self-Book Dock Appointments** app for carriers, the **Incoterm Location** will always be set to the Incoterm location retrieved from the external system (for example, TM).

  Note that the system displays this field only if the ordering party has maintained this information in their external system.

- **Country of Final Destination**

  Note that the system displays this field only if the ordering party has maintained this information in their external system.

- **Documents Verified**

  Note that this is a mandatory field. To complete the check-in or checkout process, you must select this checkbox once you have verified all the relevant documents.

Notes

Displays the additional details you have added for this gate logbook.

Attachments

Displays the attachments you have added for this gate logbook.

Vehicle Check-In

In the **Waiting for Check-In** tab, you can view the list of vehicles that are yet to be checked in the yard.

Once the vehicle arrives at the gate, you can find the appropriate gate logbook from this worklist. Once you select the appropriate gate logbook, perform the following:

1. Choose the **Start Check-In** button

   The **Start Check-In** dialog box appears.

2. Enter the following details in this dialog box:

   a. **Check-In Gate ID**

      Select the gate ID from the drop-down menu in which the vehicle is checking in.

   b. **Vehicle License Plate**

      Enter the license plate number of the vehicle.

   c. **Country or Region of Registration**

      Select the country or region of vehicle registration from the drop-down menu.

   d. **Check-In Date and Time**

      Modify the date and time of check-in if required.

3. Choose **Check-In**.

   The gate logbook details page appears.

4. In the **Vehicle Details** section, enter the following details:

   - **Vehicle Tare Weight / Unit of Measure**
   - **Vehicle Gross Weight / Unit of Measure**
   - **Maximum Payload Weight / Unit of Measure**

     The maximum payload weight must be greater than or equal to the vehicle gross weight. Note that the system validates this only when you enter the same unit of measure.

   - **Vehicle Safety**

     Note that you must select this checkbox and confirm the vehicle safety before you can proceed with the check-in of the vehicle.

5. In the **Driver Details** section, enter the following details:

   - **Driver Name and Language**
   - **Driver Phone Number**

- Driver Identification Number
- Additional Driver Name
- Additional Driver Phone Number
- Additional Driver Identification Number

Once you perform check-in, the system copies the driver details in the gate logbook to the appointment.

6. In the Resource Details section, enter the following details:
   - License Plate / Country or Region of Registration (of the truck)
   - Truck ID
   - Trailer ID
7. Optionally, in the Vehicle Seal Details section, you can choose the add icon to add seal details. Then enter the Seal Number and Seal Verification Remark to add an entry.
8. Optionally, in the Reference Documents section, you can choose the add icon to add reference documents. Then enter the Document Type and Document ID to add an entry.
9. In the Equipment section, you can add either a container or trailer by choosing the Add Equipment button and select either Container or Trailer.

   To add a container, enter the registration number and the equipment type.

   To add a trailer, enter the registration number and the trailer tare weight.

   Note

   If you have added a container, you must add the weight and seal details by choosing the Add Weight and Seal Details button. In the Weight Details tab, enter the following information:

   - Source of VGM (Verified Gross Mass) Data

     Enter the source of VGM
   - Weighing Method

     Choose whether the weighing must be based on the packed container weight or the individual item weight
   - Weight Date and Time
   - Container Tare Weight / Unit of Measure

     Enter the total weight of the container when it is empty and the unit of measure
   - Material Gross Weight / Unit of Measure

     Enter the total weight of the material including the packaging and the unit of measure
   - Dunnage Weight / Unit of Measure

     Enter the weight of the material used to load and secure cargo during transportation and the unit of measure
   - VGM (Verified Gross Mass)

     You can calculate VGM using the Calculate button.
   - Person Responsible
   - Partner Function

In the **Seal Details** tab, you can add a seal by choosing **Add**. Enter the seal number and seal verification remark and choose **Save**. You can add multiple entries.

10. Enter the additional information in the **Notes** section.
11. Add attachments using the **Add** button in the **Attachments** section.

    You can only upload files that fulfil the following criteria:

    - Files of the formats: jpg, jpeg, gif, png, pdf, doc, docx, xls, xlsx, tiff, tiff-fx
    - Image files less than 6MB file size
    - Document files less than 5MB file size
    - File name less than 150 characters including file extension
12. To proceed with the check-in, in the **Execution Documents** section, you must select the **Documents Verified** checkbox and verify the documents associated with each appointment. You can also use the **Verify Documents – Select All** button to select all the checkboxes at once.
13. Choose the **Check-In** button to complete the check-in process.

    When you choose the **Check-In** button, the system displays a dialog box. You can modify the check-in date and time and save if required. You can select one or more reason codes from the input help for check-in.

    You can also choose the **On-Hold** button to put the check-in process on hold. When you do so, you can select one or more reason codes from the input help.

    You can also choose the **Save** button to only save the document. You can come back later and complete the check-in process.

You can view the checked in gate logbooks in the **Checked In** tab on the worklist page.

Cancel Check-In

You can cancel the check-in process in gate logbooks for which the check-in is either in progress, on hold, or completed. In the gate logbook details page, when you choose the **Cancel Check-In** button, the system cancels the check-in process and the header status changes as **Check-In Canceled**. You can select one or more reason codes for cancellation from the input help. The gate logbooks with canceled check-in are displayed in the **Waiting for Check-In** tab in the worklist page.

When you navigate to the relevant appointment in the **Manage Dock Appointments** app, in the appointment details page, on the header area, you can view the **Check-In Canceled** event. Note that you can also edit or cancel the associated appointment. When you update an appointment, the associated gate logbook status changes as **Ready for Check-In**.

Note

When check-in is cancelled in the **Manage Gate Operations** app and if the gate logbook has been enabled for tracking, the event **Check-In Canceled** will be sent to your backend system.

Vehicle Checkout

In the **Checked In** tab, you can view the list of vehicles that are checked in the yard.

Once the vehicle is ready to checkout from the yard, you can find the appropriate gate logbook from this worklist.

To proceed with the checkout, you must navigate to the gate logbook details, and perform the following:

1. Choose the **Start Checkout** button

The **Start Checkout** dialog box appears.

2. Enter the following details in this dialog box:

    - **Checkout Gate ID**

      Select the gate ID from the drop-down menu in which the vehicle is checking out.

    - **Checkout Date and Time**

      Modify the date and time of checkout if required

    - **Vehicle License Plate**

      Displays the license plate number of the vehicle

3. Choose **Checkout**.

   The checkout details page appears.

4. In the **General Details** section, enter the following details:

    - **Vehicle Tare Weight / Unit of Measure**
    - **Vehicle Gross Weight / Unit of Measure**
    - **Maximum Payload Weight / Unit of Measure**

      The maximum payload weight must be greater than or equal to the vehicle gross weight. Note that the system validates this only when you enter the same unit of measure.

    - **Vehicle Safety**

      Note that you must select this checkbox and confirm the vehicle safety before you can proceed with the checkout of the vehicle.

    - **Driver Safety**

      Note that you must select this checkbox and confirm the driver details before you can proceed with the checkout of the vehicle.

    - **Reference Documents**

      Optionally, you can choose the add icon to add reference documents. Enter the **Document Type** and **Document ID** to add an entry.

5. In the **Equipment** section, if there are any containers, you must add the weight and seal details for each container by choosing the **Add Weight and Seal Details** button.

   In the **Weight Details** tab, enter the following information:

    - **Source of VGM (Verified Gross Mass) Data**

      Enter the source of VGM

    - **Weighing Method**

      Choose whether the weighing must be based on the packed container weight or the individual item weight

    - **Weight Date and Time**
    - **Container Tare Weight / Unit of Measure**

      Enter the total weight of the container when it is empty and the unit of measure

    - **Material Gross Weight / Unit of Measure**

Enter the total weight of the material including the packaging and the unit of measure

- **Dunnage Weight / Unit of Measure**

  Enter the weight of the material used to load and secure cargo during transportation and the unit of measure

- **VGM (Verified Gross Mass)**

  You can calculate VGM using the **Calculate** button.

- **Person Responsible**
- **Partner Function**

> **Note**
> The system displays the checked in weight details when you enter the checkout weight details while performing checkout. After you checkout, the system displays both the check-in weight details and the checkout weight details.

In the **Seal Details** tab, you can add a seal by choosing **Add**. Enter the seal number and seal verification remark and choose **Save**. You can add multiple entries.

6. Enter the additional information in the **Notes** section.
7. Add attachments using the **Add** button in the **Attachments** section.

   You can only upload files that fulfil the following criteria:

   - Files of the formats: jpg, jpeg, gif, png, pdf, doc, docx, xls, xlsx, tiff, tiff-fx
   - Image files less than 6MB file size
   - Document files less than 5MB file size
   - File name less than 150 characters including file extension

8. You can also choose the **Request Documents** button on the top right corner of the details page to request additional documents.
9. To proceed with the checkout, in the **Execution Documents** section, you must select the **Documents Verified** checkbox and verify the documents associated with each appointment. You can also use the **Verify Documents – Select All** button to select all the checkboxes at once.
10. Choose the **Checkout** button to complete the checkout process.

    When you choose the **Checkout** button, the system displays a dialog box. You can modify the checkout date and time and save if required. You can select one or more reason codes from the input help for checkout.

    You can also choose the **On-Hold** button to put the checkout process on hold. When you do so, you can select one or more reason codes from the input help. You can also enter additional remarks.

    You can also choose the **Save** button to only save the document. You can come back later and complete the checkout process.

You can view the checked out gate logbooks in the **Checked Out** tab on the worklist page.

> **Note**
> Once you complete the checkout process, you can open the checked out gate logbook and still add notes and attachments and choose **Save**.

Consolidated Check-In of Multiple Gate Logbooks

When a carrier confirms an appointment without entering the vehicle license plate number, the system creates a corresponding gate logbook in the **Manage Gate Operations** app without a vehicle license plate number.

The carrier has confirmed two or more appointments without a vehicle license plate number and the carrier executes these appointments in a single vehicle resource. In this scenario, the gate operator can now create a consolidated gate logbook for multiple gate logbooks corresponding to these appointments and perform check-in in the **Manage Gate Operations** app.

Once the system creates a consolidated gate logbook, the individual logbooks are canceled automatically, and the system updates the associated external systems, gates, yards, and business partners with this updated gate logbook ID through API.

Example

The carrier confirms an appointment APT11. The system creates a corresponding gate logbook GLB11 in the **Manage Gate Operations** app. Similarly, the carrier confirms an appointment APT22. The system creates a corresponding gate logbook GLB22. The carrier executes appointments APT11 and APT22 in the same vehicle resource.

When the vehicle arrives at the gate, the gate operator is aware of the appointments and gate logbooks associated with this vehicle. The gate operator selects the associated gate logbooks and chooses **Start Check-In**.

The gate operator enters the following information and begins the check-in process:

- **Check-In Gate ID**
- **Vehicle License Plate**
- **Country or Region of Registration**
- **Check-In Date and Time**

The system now creates a consolidated gate logbook GLB33 and cancels the previously created gate logbooks GLB11 and GLB22. The system sends this information to the associated external systems, gates, yards, and business partners through API.

The system uses the message code 11200 to send a message that gate logbook GLB11 and GLB22 are canceled as the license plate number was updated and that the user must refer to the new gate logbook GLB33.

Enabling Dock Appointment Scheduling for Guest Users

SAP Business Network for Logistics enables you to interact and schedule appointments with customers and carriers who are not onboarded as business partners in SAP Business Network for Logistics.

As a shipper, when you enable your customers to pick up orders from your warehouse, you can associate with both customers who are onboarded and who are not onboarded. When you request for an appointment using the appointment request API, the system sends the appointment request with the email address of your customer or consignee.

If the customer or consignee is not onboarded in SAP Business Network for Logistics, the system creates an appointment and sends this appointment to the guest customer in an email notification. The guest customer can sign in using the guest URL and can either assign carriers or can decide to execute the transportation on their own.

If the guest customer decides to execute the transportation on their own, then they can directly book an appointment. However, if they decide to outsource the transportation to a carrier, then the user can provide the email address of the carrier in the Assign Carrier section available in the guest user UI. When the customer provides the email address, SAP Business Network for Logistics receives the information and sends an email notification to the guest carrier user.

The guest carrier user receives an email notification to book an appointment. When the user books an appointment, the system creates a confirmed dock appointment and sends it to your external transportation system.

For more information on how the customer or carrier can use the guest user URL, see Maintaining a Dock Appointment (Guest User).

ℹ Note

Only those business partners who are onboarded in SAP Business Network for Logistics have an LBN ID. The guest carrier user or the guest customer will not have an LBN ID as they are not onboarded in SAP Business Network for Logistics.

In the **General Settings** app, in the **Define Appointment and Dispute Settings** tab, you can choose the **Guest User Access** button to define the type of URL you want to send to the guest carrier user.

- **Dynamic URL**

  When you select this option, the system sends a URL to the carrier which is specific to the document you send to the carrier for dock appointment scheduling. The carrier can enter the document reference to view the document.

- **Static URL**

  When you select this option, the system sends a URL to the carrier which is generic. The carrier can enter the following details and view the document:

  - **Document Type and ID**
  - **Email ID**
  - **User Name**
  - **Company Name**

  We recommend you to select the dynamic URL by default. If you select the static URL, anyone with the link and valid document reference can access the document.

For more information, see Appointment and Dispute Settings.

ℹ Note

If you select the dynamic URL option and later change the setting to static URL, the guest user can use both the dynamic and static URLs to access the document. However, if you select the static URL and later change the setting to dynamic URL, the guest user can only use the latest dynamic URL to access the document.

For more information on the appointment API implementation considerations, see the **Guest User Access** section in Provider API for Dock Appointment Scheduling.

Track Freight Movement

The **Track Freight Movement** app keeps you informed of the execution of your freight documents by tracking and displaying the following information:

- Planned and unplanned events in a freight document

  The system displays the events in a freight order that were manually reported by your carrier in the **Freight Orders for Reporting** app. From Transportation Management (TM) on SAP S/4HANA system version 1909 onwards, the tracked data is also synchronized to your Transportation Management (TM) on SAP S/4HANA system.

- Carrier's automated visibility data (including real-time location, estimated ETA (expected time of arrival), and time of event completion) from a supported visibility provider, if available.

Note that this app has been deprecated and will be sunset shortly. This app has been replaced with the new app **Manage Freight Execution**.

You can do the following in the **Track Freight Movement** app:

- Search for a freight document and view its general information.
- Track planned and unplanned events occurred during freight execution.
- Monitor visualized freight execution flow.
- Monitor tracked events and shipping routes in a map view.
- View Proof of Delivery and Proof of Pickup documents uploaded by your carrier.
- Find the freight document IDs of reference business documents.

ℹ Note

To use this app, you must add one or several roles to your role collection. The required role templates and application identifiers are described in the Available Roles for Shippers section of the Administration Guide for Shippers.

Worklist (Track Freight Movement)

The **Track Freight Movement** app consists of a main view and a detailed view.

When you open the app, the main view is displayed. It consists of two screen areas:

- Filter bar

  Using the filter bar in the header, you can filter the freight documents by one of the following criteria to restrict the number of freight documents displayed:

  - **Freight Document**
  - **Reference Document**
  - **Container**
  - **Shipping Type**
  - **Carrier**
  - **Planned Departure Date**
  - **Planned Arrival Date**
  - **Source Location**
  - **Source Country**
  - **Destination Location**
  - **Destination Country**
  - **Process Status**
  - **Execution Status**

  To adjust the filters, choose **Adapt Filters**.

- **Freight Documents** list

  Displays the freight documents filtered by your settings in the filter bar. You can control the fields to be shown for each freight document by choosing the settings icon.

The system displays the following fields in the **Freight Documents** worklist:

- **Freight Document/Freight Document Type**

  Displays the ID of the freight document and the type of the freight document for which the execution has been planned. When you choose the freight document, the system displays additional details of the freight document in a dialog box. You can also directly navigate to the freight document by choosing **More Info**.

  Note that you must maintain the necessary settings in the **System Connections** app for the system to navigate to the freight document. For more information, see System Connections.

- **Carrier**

  Displays the details of the carrier. When you choose the carrier, the system displays the additional details of the carrier.

- **Planned Departure and Planned Arrival**

  Displays the location of planned departure and planned arrival. When you choose the location, the system displays the additional details of the location. You can also view the latitude and longitude details of the location by choosing the globe icon.

  Note that the location name displayed in the **Track Freight Movement** app corresponds to the location name you have maintained in the location master data in your SAP Transportation Management (SAP TM) system. If you have not specified a location name, then the system uses the location ID in your SAP TM system.

- **Source Country** and **Destination Country**

  Displays the source and destination country that you have maintained in the location master data.

- **Execution Status**

  Displays whether the freight is **Ready for Execution** or **In Transit**. For more information, see Execution Status, Process Status, and Event Status.

- **Process Status**

  Displays whether the freight execution is **As Planned**, **Early**, **Late**, **Overdue**, or **Delayed**. For more information, see Execution Status, Process Status, and Event Status.

Apart from the above fields, you can add one or more of the following fields to the worklist from the settings icon in the worklist:

- **Cargo Quantity**
- **Cargo Quantity UoM**
- **Cargo Volume**
- **Cargo Volume UoM**
- **Cargo Weight**
- **Cargo Weight UoM**
- **Carrier External ID**
- **Container**
- **Dangerous Goods**
- **Destination Location**
- **Estimated Arrival At**
- **Estimated Arrival Time Zone**
- **IMO**