The **Attachments** section displays the attachments the ordering party has sent you, as well as letting you upload your own attachments.

Accepting a Freight Request for Quotation

If you agree with the price and the dates given by the ordering party, you can accept a freight request for quotation (freight RFQ) without proposing a change.

Context

You can also accept a freight RFQ that you previously rejected or accepted with a change, as long as the freight RFQ has not been closed by the ordering party.

If you want to propose a new price or new dates, see Accepting a Freight Request for Quotation with a Change.

Procedure

1. Open the **Freight Requests for Quotation** app.
2. Within a worklist (**New**, **Responded To**, or **All**), select one or more open freight RFQs (a freight RFQ is open if its remaining time has not ran out). To accept a single freight RFQ, you can also use the detail view.
3. Choose **Accept**.

   Note that if one or more of the selected freight RFQs contain zero prices from the ordering party and if you have not maintained any price, the system displays a warning message before you proceed to **Accept**. The ordering party expects you to enter a price before you accept.

Next Steps

Your ordering party will now evaluate your freight quotation and reply to it. If they award it to you, they will ask you to confirm the related freight order in the **Freight Orders for Confirmation** app.

Accepting a Freight Request for Quotation with a Change

You can accept a freight request for quotation (freight RFQ) with a change.

Context

If the ordering party wants to receive proposals for alternative prices or dates to those which they specified in the freight request for quotation (freight RFQ), then you can make a proposal by accepting the freight RFQ with a change. And, as long as the remaining time has not run out and the freight RFQ has not been closed by the ordering party, you can accept a freight RFQ and make a date or price proposal for freight RFQs that you previously rejected or accepted.

ℹ Note

The ordering party can maintain a setting in their transportation management system to either enable or disable you from modifying the price proposal currency. Based on this setting, when you accept a freight request for quotation with change, the system either enables you to modify the price proposal currency or does not allow you to do so. You can view these details in the information icon next to the price proposal currency, in the dialog box, which appears when you choose the **Accept with Change** button in the freight request for quotation.

Note that when you change the price proposal currency, the system automatically updates the settlement currency to be the same as the updated price proposal currency.

Procedure

1. Open the **Freight Requests for Quotation** app.
2. Within a worklist (**New**, **Responded To**, or **All**), look for the open freight RFQ for which you want to enter changes (a freight RFQ is open if its remaining time has not ran out). Alternatively, you can also open the detail view of the freight RFQ.
3. Choose **Accept with Change**.
4. Enter your your proposal price and the currency.
5. Enter your date proposals. For each stop, the earliest start and the latest end for all activities at that location are displayed, such as driving on the premises, loading, completing paper work. These dates might be prefilled by your ordering party. In the proposal fields in the middle, you can see if the ordering party would prefer a timeframe for your activities. If these are empty, you can enter your own proposal in these fields.
6. Choose **Accept with Change**.

Next Steps

Your ordering party will now evaluate your freight quotation and reply to it. If they award it to you, they will ask you to confirm the related freight order in the **Freight Orders for Confirmation** app.

Rejecting a Freight Request for Quotation

You can reject a freight request for quotation (freight RFQ) if you are unable to or do not want to take over this transport.

Context

As long as the remaining time to respond hasn't ran out and the freight RFQ has not been closed by the ordering party, you can reject a freight RFQ, even if you previously accepted it.

Procedure

1. Open the **Freight Requests for Quotation** app.
2. Within a worklist (**New**, **Responded To**, or **All**), select one or more open freight RFQs (a freight RFQ is open if its remaining time has not ran out). To reject a single freight RFQ, you can also use the detail view.
3. Choose **Reject** and select a rejection reason. Note, the reject reason will be assigned to **all** selected freight RFQs and recorded in each automatically generated freight quotation.
4. Choose **Reject**.

Freight Quotations

The **Freight Quotations** app allows you to see if the ordering party awarded or rejected the freight requests for quotation (freight RFQs) that you submitted to them.

The **Freight Quotations** app consists of a main view and a detail view:

When you first open the app, the main view is launched, which has two screen areas:

- Filter bar

Using the filter bar in the header, you can filter the freight quotations by one or more of the following attributes to restrict the number of freight quotations displayed:

  - My latest response
  - Ordering party
  - Departure date
  - Departure location
  - Arrival date
  - Arrival state
  - Currency
  - Departure state
  - Freight Quotation
  - Ordering party response
  - Submitted price
  - Vendor ID

- Worklists

  You can use the following worklists: **Response Received**, **No Response Received** and **All**.

From the main view, you can navigate to the detail view, which has two screen areas:

- Header

  You can display data such as the latest submitted price, your latest response and the response of the ordering party.

- Sections

  You can display further details in the **Information**, **Cargo**, **Tour**, **Contacts**, **Notes**, and **Attachments** sections.

E-mail notifications are sent to carriers when the following events are triggered in tendering and subcontracting:

- Award Quotation – when a quotation is awarded to the carrier by the shipper for the RFQ
- Reject Quotation – when a quotation is rejected by the shipper for the RFQ

The notifications include a link that the user can click to view the relevant status or perform any action they need to carry out. The e-mail also includes a request to perform the necessary action on or before a specific date.

Worklist (Freight Quotations)

To restrict the number of freight quotations displayed, you can use the preconfigured worklists (**Response Received**, **No Response Received**, **All**) according to the status of the freight quotation.

Response Received

The **Response Received** worklist displays the freight quotations that have been responded to by the ordering party. For each freight quotation, the following information is displayed:

- Ordering party and freight quotation
- Departure date and time
- Departure location and arrival location
- Ordering party response
- Submitted price
- Vendor ID

The freight quotations are only displayed if the departure date and time has not yet been reached.

No Response Received

The **No Response Received** worklist displays all freight quotations that haven't yet been responded to by the ordering party. For each freight quotation, the following information is displayed:

- Ordering party and freight quotation
- Departure date and time
- Departure location and arrival location
- Response due date and time of the freight RFQ
- Submitted price
- Vendor ID

The freight quotations are only displayed if the departure date and time has not yet been reached.

All

The **All** worklist displays all freight quotations. For each freight quotation, the following information is displayed:

- Ordering party and freight quotation
- Departure date and time
- Departure location and arrival location
- My latest response
- Ordering party response
- Submitted price
- Vendor ID

The **All** worklist displays all freight quotations:

- that the ordering party has already responded to
- that the ordering party has not yet responded to
- that the ordering party has already closed

Therefore, the number of freight quotations displayed in the **All** worklist can be higher than the sum of those displayed in the **Response Received** and **No Response Received** worklists altogether.

Detail View (Freight Quotation)

The detail view of a freight quotation consists of a header and several sections.

Header

The **Header** section displays important data about the freight quotation as well as data related to the response you submitted to your ordering party.

The following fields may be of particular interest to you:

- Your latest response (**Accepted**, **Accepted with Change**, **Rejected**, **Accepted Automatically**)
- Your latest submitted price
- The response of your ordering party (**Award Pending**, **Awarded**, **Rejected**)
- Contact details of the ordering party

Information

The information section displays the following details:

- General data section

  Displays the freight order, total distance, total duration, response due date and time, number of loading and unloading stops, mode of transport, and total gross weight, volume, and quantity.

  Note that in the **Assign Codes** app, if you do not maintain the mapping between **Code in External System** and **LBN Code** for the values in the below table, then the system does a default mapping to the respective value.

  Mode of Transport

SAP Transportation Management System	SAP Business Network for Logistics System
03 - Ocean	01 - Ocean
01 - Road	03 - Road
05 - Air	04 - Air

- Departure location section

  Displays the date and time of departure and address of departure location.

- Arrival location section

  Displays the date and time of arrival and address of arrival location.

- Transport requirements section

  Displays whether you have opted to view the details of dangerous goods and the temperature requirements.

ℹ Note

If the ordering party has entered dangerous goods information in their SAP Transportation Management (TM) system, this information is transferred to SAP Business Network for Logistics. To view this information, in the **Information** section, choose **Yes** under **Dangerous Goods**, which opens a window containing details about the item type, relevant regulations, and more detailed information such as storage instructions, temperature control, and emergency temperature. You can choose to display the dangerous goods information in any language that the ordering party has specified previously in the TM system.

- Terms and conditions

  Displays the incoterm and incoterm location.

  Note that you can view the incoterm location details that the ordering party has added in the **Manage Locations** app. If the ordering party has not added this information, you can view the text specified for incoterm location in the ordering party's external transportation system.

- Administrative data section

  Displays the date and time the freight order was received, details of the last responded person and time.

Submitted Quotations

The **Submitted Quotations** section displays all the freight quotations that were created by you accepting or rejecting the freight request for quotation (freight RFQ).

The following fields may be of particular interest to you:

- Freight quotation ID along with your response (**Accepted**, **Accepted with Change**, **Rejected**, **Accepted Automatically**)
- Price
- Response of the ordering party (**Award Pending**, **Awarded**, **Rejected**)
- Start and end dates

  For each stop within the stop sequence, the following dates for all activities at that location are displayed:

  - Earliest start and latest end (this is, the hard borders given by the ordering party)
  - Proposed start and proposed end (this is, either the more narrow timeframe entered by your ordering party, or your own new proposal)

Cargo

The **Cargo** section displays data about the cargo items involved, such as weight, quantity, and special transport requirements.

The following fields may be of particular interest to you:

- Item ID

  You might need the item ID to clarify with your ordering party open issues regarding a cargo item.

- Dangerous Goods

  If the ordering party has provided dangerous goods information, you can view this information from the **Cargo** section by choosing **Yes** in the **Dangerous Goods** column. This opens a window containing details about the item type, relevant regulations, and more detailed information such as storage instructions, control temperature, and emergency temperature.

When you choose **View Stage and Step Details**, you can display details about the cargo in the context of stops and transportation stages:

- Stops

  For each stop within the stop sequence, the address of the ordering party and the cargo items to load or unload are displayed.

- Stages

  For each transportation stage, the cargo items to be loaded or unloaded are displayed.

> **Note**
> You can view the details of all cargo item types such as container, package, product, and service. You can navigate through the entire cargo item hierarchy. For example, from a container to the packages, package to the products or services and so on to view the respective details.

Tour

The **Tour** section displays the stop sequence. For each stop, you can view data such as the address location, the dates and times, and the loading or unloading activity at the location.

Contacts

If provided by the ordering party, the **Contacts** section displays the company name of the ordering party along with the phone number and the email address of the contact person. This section also displays the contact details for each individual stop (stop number and location).

Notes

The **Notes** section displays the comments previously left by the ordering party and yourself.

Attachments

The **Attachments** section displays the files the ordering party sent you with the freight request for quotation as well as the attachments you sent to the ordering party when you responded.

Freight Orders for Confirmation

The **Freight Orders for Confirmation** app allows you to confirm freight orders that ordering parties ask you to execute in subcontracting.

SAP Business Network for Logistics has integrated with the SAP ERP Central Component (SAP ECC) LE-TRA shipments, and SAP Logistics Management consignment orders. **Freight Orders for Confirmation** app allows you to view them.

The **Freight Orders for Confirmation** app consists of a main view and a detail view.

When you first open the app, the main view is launched. It has two screen areas:

- Filter bar

Using the filter bar in the header, you can filter the freight orders by one or more of the following attributes to restrict the number of freight orders displayed:

- Freight order
- Ordering party
- Departure date
- Departure location
- Freight order status
- Shipping type
- Driver name
- License plate
- Reference document type
- Reference document ID
- Arrival date
- Requested Loading Start Date Time
- Requested Loading End Date Time
- Acceptable Loading Start End Time
- Acceptable Loading End Date Time
- Transport means description
- Transport means type
- Dangerous goods
- Arrival location
- Arrival state
- Departure state
- Document category
- Scenario
- Shipping type code
- Vehicle category code
- Vehicle type code
- Vendor ID

- Worklists

  You can use the following worklists: **New**, **Responded To (Open)**, and **All**.

From the main view, you can navigate to the detail view, which has two screen areas:

- Header

You can display data such as the price, the remaining time, the contact details of the ordering party and your latest response.

- Sections

  You can display further details in the **Information**, **Cargo and Service Items**, **Charges**, **Tour**, **Contacts**, **Notes**, **Attachments**, and **Drivers and Resource Details** sections.

Email notifications are sent to carriers when the following events are triggered in tendering and subcontracting:

- Create Freight Order for Confirmation – when a new freight order is created in SAP Business Network for Logistics
- Update Freight Order for Confirmation – when a freight order is updated in SAP Business Network for Logistics
- Cancel Freight Order for Confirmation – when a freight order is canceled by the shipper

The notifications include a link that the user can click to view the relevant status or perform any action they need to carry out. The email also includes a request to perform the necessary action on or before a specific date. The Award Freight Order notification is already covered by the confirmation notification.

New Version

You can now use the latest version of the **Freight Orders for Confirmation** app.

When you login and use the app for the first time, you will automatically be navigated to the new version of the app. You can also switch to the old version using the button in the dialog box that appears automatically when login for the first time.

The following enhancements have been made in the new version of the app:

Switch Versions

A new toggle button has been introduced in the worklist page to switch between the old version and the new version of the app.

Response Required Filter

You can view the **Response Required** filter on the header area of the worklist page. You can filter freight orders based on whether you must respond to the freight order or not by choosing the options **Yes** and **No**.

Freight Order Status Labels and Icons

In the worklist page, in the **Freight Order Status** column, along with the freight order status you can view whether the freight order has been updated. You can also view whether you need to respond to the freight order. The same information also appears on the details page on the header area.

New Worklist Tabs

You can view the following tabs in the worklist:

- **All**
- **New**
- **Confirmed**
- **Rejected**
- **Cancelled**

Freight Order Statuses

The freight order can have one of the following statuses:

- New
- Updated
- Confirmed
- Rejected
- Confirmed Automatically
- Cancelled

  Note that the freight order can be cancelled only when there is no active dispute or an invoice document corresponding to the freight order.

- Cancellation Confirmed

All and Updated Subtabs

In the worklist page, in the New tab, you can view the All and Updated subtabs. In the All subtab, you can view all new and updated freight orders that are active to respond and whose planned arrival time at the final destination has not yet passed. In the Updated subtab, you can view all freight orders that have received an update from the ordering party after your response and whose planned arrival time at the final destination has not yet passed.

New Message for Updated Freight Orders

A message appears on the worklist page if the ordering party has updated a confirmed or rejected freight order and sent it to you. This message provides information on how many confirmed or rejected freight orders have been updated today. You can use the link in this message to directly navigate and view all the updated freight orders.

Worklist (Freight Orders for Confirmation)

To restrict the number of freight orders displayed, you can use the preconfigured worklists (New, Responded To (Open), All) according to the status of the freight order.

Freight Order Worklist Transition Based on the Status

When the ordering party updates or cancels a confirmed freight order in their SAP Transportation Management system and sends it you, the system displays it in the New tab. When the arrival or departure date and time of a freight order is in the future, the system displays it in the New tab.

When you confirm this freight order from the New tab, the system moves it to the Responded To tab.

If the ordering party updates this freight order again in their SAP Transportation Management system, the system again moves it to the New tab.

If the departure or arrival date and time of a freight order is in the past, or if the remaining time to respond has expired, the system displays it in the All tab.

All