10.2 Machines

Machine: a tool used to make work easier.

 Machines make work easier to do by providing some trade-off between the force applied and the distance over which the force is applied.

 They change the size or the direction of the applied force.

• EX: Bottle opener

Terms and Equations

- Effort Force (F_E) the force applied to a machine
- Effort Distance (D_E) the distance through which the machine moves
- Work Input (W_I) work done on a machine $W_I = F_E \times D_E$
- Resistance Force (F_R) the force applied by the machine
- Resistance Distance (D_R) the distance through which the object moves
- Work Output (W_O) work done by a machine $W_O = F_R \times D_R$

Machines

- Machines can multiply force.
- Machines do not multiply work.
- Work output cannot be greater than work input.
- Ideal Work: $W_I = W_O$
- Mechanical Advantage (M.A.) the number of times a machine multiplies the effort force.

$$M.A. = F_R / F_E$$

Mechanical Advantage = F_R/F_E

- M.A. equal to 1:
 - machine does not multiply the effort force, it just changes the direction of the effort force.
 - EX: Simple pulley
- M.A. is less than one:
 - machine increases the distance an object is moved.
 - EX: Hockey stick
- M.A. greater than one:
 - machine increases the force applied by the person.
 - EX: Car jack

Mechanical Advantage:

$$M.A. = F_r / F_E$$

Ideal $M.A. = d_E / d_r$

Efficiency of a machine:

- The comparison of work output to work input
- Expressed as a percent
- Can never be greater than 100%
- Friction reduces the efficiency of a machine.
 Anything that reduces friction such as keeping a machine well lubricated increases efficiency.

Efficiency of a machine

% Efficiency = $W_O / W_I \times 100 = MA/IMA \times 100$

- Example: What is the efficiency of a machine where work input is 200 J, and work output is 100 J?
- % Efficiency = $100 \text{ J} / 200 \text{ J} \times 100 = 50\%$


Compound Machine

- A machine consisting of two or more simple machines linked in such a way that the Fr of one machine becomes the effort force of the second.
 - EX: Bike p.270
- MA/IMA of a compound machine is the product of the MAs/IMAs of the simple machines.

Lever

- A lever is a stiff rod that rotates around a pivot point.
 - Depending on where the pivot point is located, a lever can either change the force applied or the distance over which the force is applied.

1st Class lever











2nd Class lever













3rd Class Lever












Inclined Plane





 An inclined plane is a ramp used to gradually move an object up/down.





- An inclined plane wrapped to form a spiral
- It reduces effort force by increasing effort distance.


Wedge


A wedge converts
 motion in one direction
 into a splitting motion
 that acts at right angles
 to the blade.





Pulley System


- A single pulley simply reverses the direction of a force.
- When two or more pulleys are connected together, they permit a heavy load to be lifted with less force by increasing the distance.
- The M.A. of a pulley system is approximately equal to the amount of supporting ropes or strands.























Wheel and axle

- A wheel and axle is a lever that rotates in a circle around a center point or fulcrum. The larger wheel rotates around the smaller wheel (axle).
 - EX: Bicycle wheels.





- EX: The rear wheel on your bike has a radius of 35.6 cm and has a gear with a radius of 4 cm. When the chain is pulled with a force of 155 N, the wheel rim moves 14 cm. The efficiency of this part of the bike is 95%.
- a) What is the IMA of the wheel and gear?
- b) What is the MA of the wheel and gear?
- c) What is the resistance force?
- d) How far was the chain pulled to move the rim 14 cm?