

Automate

For DaVinci Resolve Studio & Fusion Studio 21

Installing

Make sure you chose the correct installer:

- `Install Automate.pkg` installer for **MacOS**
- `Install Automate.exe` installer for **Windows**

To run the installer, double click it and follow the on screen instructions. You can also choose to install Additional Presets and Examples and to install Automate for Fusion Studio if available.


Requirements

Before buying Automate, you will need:

- DaVinci Resolve **Studio** 21
- **MacOS** 26 or **Windows** 11

Automate Modifier

You can add an Automate modifier to almost any property in a Fusion Composition by right-clicking it in the inspector and locating Automate in the "Modify With" menu.



Start / Hold - Once you've added an Automate modifier, you should see two keyframes appear. These keyframes correspond to the **Start** and **Hold** sliders in the Modifiers inspector window.

Duration - You can change the length of the animation (in **Frames** or **Seconds**) using the **Duration** slider. If you select a Duration longer than the duration of the Fusion Composition, it will automatically be reduced to fit into the duration of the fusion composition.

Easing - How the animation looks between the **Start** and **Hold** frames. You can change the easing type to be **Linear**, **Easing**, or **Custom**. If you select Custom, you can draw your own Easing Curve in the inspector.

Direction - The type of animation:

- **In** - Animate at the **Start** of the clip
- **Out** - Animate at the **End** of the clip
- **Both** - Animate **In** and **Out**

Autosync Modifier

Automate also comes with the **Autosync** Modifier. The Autosync Modifier works similarly to the regular Automate Modifier but **without** the **timing controls**. Instead, it shares them with an existing Automate Modifier.



Sync - You must select an **Automate** to sync to:

- Locate the text "**Right-click to sync with Automation**" and right-click it.
- Locate the "**Connect To**" menu
- Select the Automate you wish to sync to

Easing - If you would like to override the **Easing** controls for an Autosync Modifier, locate the Easing setting and change it from **Sync** to **Custom**.

Automate Node



You can use the **Automate Node** when you wish to create a group of **Autosync** animations with shared controls. It works very similarly to the **Automate Modifier** but without its own **Start/Hold/End** values.



You can also chain **Automate Nodes** to play animations one after another by connecting the the nodes together in the order you want them to play in.

More Control

Automate has extra quality-of-life controls hidden in right-click menus and button combos.

Defaults - You can right click almost any setting in Automate and select "Save Default for ..." to save that setting as a new default for all Automate/Autosync nodes at once.

Timing - You can right-click the Duration / Delay sliders to set their values based on the position of the playhead.

Shift - You can hold shift while dragging the control Automate is connected to to change **Start**, **Hold** and **End** simultaneously.

Motion Blur - Automate uses its Smart Cache to skip slow Motion Blur effects when **static graphics** like text aren't moving. However, if you're animating a MediaIn **video clip** you'll need to do this manually. You can right-click on the **Name** of an Automate Tool in the **Inspector** and select **Publish Motion Blur**. This will create an additional output you can connect to a **Motion Blur** checkbox to disable Motion Blur while the animation is inactive.

Extra Settings - If you right-click the title of a tool, you will see some extra settings including **Smart Cache** settings and the option to move the **Automate Modifiers** into the **PizzaBluFX** submenu.

Hidden Nodes

If you are interested in creating macros with Automate, it comes with several hidden nodes that can help you. You can access the hidden nodes by pasting the snippets below:

```
{Tools = ordered() {MotionBlurGroups1 = PizzaBlu.Automate.MotionBlurGroups {}}}
```

```
{Tools = ordered() {PositionButtons1 = PizzaBlu.Automate.PositionButtons {}}}
```

```
{Tools = ordered() {SliderGroup1 = PizzaBlu.Automate.SliderGroup {}}}
```

```
{Tools = ordered() {Outline1 = PizzaBlu.Automate.Outline {}}}
```

```
{Tools = ordered() {Blank1 = PizzaBlu.Automate.Blank {}}}
```

Macro Snippet

If you already understand how to edit a fusion settings file, the following code snippet may be copy-pasted to quickly include all of automates controls.

```
Automate1_Direction = InstanceInput { SourceOp = "Automate1", Source = "Direction" },
Automate1_Time = InstanceInput { SourceOp = "Automate1", Source = "Time" },
Automate1_SyncSource = InstanceInput { SourceOp = "Automate1", Source = "SyncSource" },
Automate1_Units = InstanceInput { SourceOp = "Automate1", Source = "Units" },
Automate1_DurationFramesIn = InstanceInput { SourceOp = "Automate1", Source = "DurationFramesIn", Default = 60 },
Automate1_DurationFramesOut = InstanceInput { SourceOp = "Automate1", Source = "DurationFramesOut", Default = 60 },
Automate1_DurationSecondsIn = InstanceInput { SourceOp = "Automate1", Source = "DurationSecondsIn", Default = 1 },
Automate1_DurationSecondsOut = InstanceInput { SourceOp = "Automate1", Source = "DurationSecondsOut", Default = 1 },
Automate1_DelayFramesIn = InstanceInput { SourceOp = "Automate1", Source = "DelayFramesIn", Default = 0 },
Automate1_DelayFramesOut = InstanceInput { SourceOp = "Automate1", Source = "DelayFramesOut", Default = 0 },
Automate1_DelaySecondsIn = InstanceInput { SourceOp = "Automate1", Source = "DelaySecondsIn", Default = 0 },
Automate1_DelaySecondsOut = InstanceInput { SourceOp = "Automate1", Source = "DelaySecondsOut", Default = 0 },
["Automate1_AutomationIn.Nest"] = InstanceInput { SourceOp = "Automate1", Source = "AutomationIn.Nest" },
["Automate1_AutomationIn.Type"] = InstanceInput { SourceOp = "Automate1", Source = "AutomationIn.Type" },
["Automate1_AutomationIn.EaseIn"] = InstanceInput { SourceOp = "Automate1", Source = "AutomationIn.EaseIn", Width = 0.5 },
["Automate1_AutomationIn.EaseOut"] = InstanceInput { SourceOp = "Automate1", Source = "AutomationIn.EaseOut", Width = 0.5 },
["Automate1_AutomationIn.CustomIn"] = InstanceInput { SourceOp = "Automate1", Source = "AutomationIn.CustomIn" },
["Automate1_AutomationOut.Nest"] = InstanceInput { SourceOp = "Automate1", Source = "AutomationOut.Nest" },
["Automate1_AutomationOut.Type"] = InstanceInput { SourceOp = "Automate1", Source = "AutomationOut.Type" },
["Automate1_AutomationOut.EaseIn"] = InstanceInput { SourceOp = "Automate1", Source = "AutomationOut.EaseIn", Width = 0.5 },
["Automate1_AutomationOut.EaseOut"] = InstanceInput { SourceOp = "Automate1", Source = "AutomationOut.EaseOut", Width = 0.5 },
["Automate1_AutomationOut.CustomOut"] = InstanceInput { SourceOp = "Automate1", Source = "AutomationOut.CustomOut" },
Automate1_BrandIcon = InstanceInput { SourceOp = "Automate1", Source = "BrandIcon" },
Automate1_BrandLink = InstanceInput { SourceOp = "Automate1", Source = "BrandLink" },
```

Tip: You can **find** and replace for "**Automate1**" if your Automate node has a different name.