AWS Cloud Practical

Name: Pooja Prakash Belgaumkar

1. Enable Flow Logs for a subnet and view traffic in CloudWatch.

- Flow Logs capture IP traffic going to and from network interfaces, subnets, or VPCs.



- Create a flow log for the VPC subnet to monitor incoming and outgoing IP traffic.
- Open VPC Console → Subnets → Select your subnet
- Click Actions → Create Flow logs
- Select Destination **Send to CloudWatch Logs**
- Select Filter **All** to record both Accept and Reject logs
- Create and use new service **IAM Role** it is necessary to allow VPC Flow Logs to send network traffic logs to CloudWatch Logs.

VPC > Subnets > Create flow logs

Create flow log Info

Flow logs can capture IP traffic flow information for the network interfaces associated with your resources. You can create multiple flow logs to send traffic to different destinations.

Selected resources Info

Flow logs will only be created for resources in an available state.

Name	Resource ID	State
subnet2	subnet-02a8673f206ec59d0	Available

Flow log settings

Name - *optional*

my-flow-log-01

Filter

The type of traffic to capture (accepted traffic only, rejected traffic only, or all traffic).

- ( ) Accept
- ( ) Reject
- (•) All

Maximum aggregation interval Info

The maximum interval of time during which a flow of packets is captured and aggregated into a flow log record.

- (•) 10 minutes
- ( ) 1 minute

VPC > Subnets > Create flow logs

Destination

The destination to which to publish the flow log data.

- (•) Send to CloudWatch Logs
- ( ) Send to an Amazon S3 bucket
- ( ) Send to Amazon Data Firehose in the same account
- ( ) Send to Amazon Data Firehose in a different account

Destination log group Info

The name of an existing log group or the name of a new log group that will be created when you create this flow log. A new log stream is created for each monitored network interface.

Subnet-2-Flowlogs

Service access

VPC flow logs require permissions to create log groups and publish events in CloudWatch.

- ( ) Use an existing service role
- (•) Create and use a new service role

Service role name Info

VPCFlowLogs-Cloudwatch-1768406300488

Log record format

Specify the fields to include in the flow log record.

- (•) AWS default format
- ( ) Custom format

- We can see log streams after some time of traffic exits.
- We will see entries under log stream of subnet.
- Where, ACCEPT → traffic allowed

  REJECT → traffic blocked by SG/NACL





- ➢ VPC Flow Logs were enabled on the subnet to capture network traffic and send logs to CloudWatch for monitoring and troubleshooting.