# Course Introduction (contd.): Operating Systems

Mainack Mondal and Saptarshi Ghosh

CS31202 / CS30002



#### The story so far

- What is an OS
- What are the two goals of an OS
- Two key parts of OS
- Interrupt driven functionality of OS

#### Today's class

- A brief historical overview of OS
  - Batch processing systems
  - Multiprogramming
  - Multitasking

- Today's OS (multitasking, like Unix)
  - Dual mode of operation
  - Uses of timer

### A brief history of OS


#### The beginning

Computers == which performs computational tasks

#### The beginning

Computers == which performs computational tasks






Give a job: It will give you output

#### The beginning

Computers == which performs computational tasks






Give a job: It will give you output What if you had to compute multiple jobs?

#### First computers were similar

- Thus the operating system was simply designed
  - Batch processing operating system
  - One job executed at a time
  - Only one job in memory at one time and executed (till completion) before the next one starts

#### First computers were similar

- Thus the operating system was simply designed
  - Batch processing operating system
  - One job executed at a time
  - Only one job in memory at one time and executed (till completion) before the next one starts



https://youtu.be/YXE6HjN8heg?t=308

#### Problem with batch processing

A job has to wait for another to finish

- Led to very high wait times for the following jobs
- Under-utilization of CPU

#### Problem with batch processing

A job has to wait for another to finish

- Led to very high wait times for the following jobs
- Under-utilization of CPU

Insight: Input/Output from peripherals were very slow

 Your job has to wait forever when my job is simply reading the necessary data from peripheral devices

#### Problem with batch processing

A job has to wait for another to finish

- Led to very high wait times for the following jobs
- Under-utilization of CPU

Insight: Input/Output from peripherals were very slow

 Your job has to wait forever when my job is simply reading the necessary data from peripheral devices

Insight: A typical job usually has two types of phases in its lifetime - (1) when it uses CPU, (2) when it does I/O

#### **SPOOLing**

Simultaneous Peripheral Operations On-Line (SPOOL)

Only start jobs when all required data is read

OR, Send data output to a SPOOL buffer / virtual device





#### **SPOOLing**


- A spool is a buffer that holds output for an I/O device (usually a device such as a printer, that cannot accept interleaved data streams)
  - Read as far ahead as possible from input devices
  - Store output data until output devices are able to accept them

A part of the disk can actually be used as a spool

CPU







### SPOOLing brings in important concepts

- Addition of I/O processors
  - Overlap the I/O of one job with computation of other jobs
  - Better utilization of CPU
- Concept of virtual device
- Multiple jobs simultaneously reside in memory (CPU to be allocated to one of them at a time)
- CPU-bound and I/O-bound jobs

### SPOOLing brings in important concepts

- Addition of I/O processors
  - Overlap the I/O of one job with computation of other jobs
  - Better utilization of CPU
- Concept of virtual device
- Multiple jobs simultaneously reside in memory (CPU to be allocated to one of them at a time)
- CPU-bound and I/O-bound jobs
   Spooling is a special form of multiprogramming

#### Today's class

- A brief historical overview of OS
  - Batch processing systems
  - Multiprogramming
  - Multitasking

- Today's OS (multitasking, like Unix)
  - Dual mode of operation
  - Uses of timer

#### Multiprogramming

- Multiple jobs loaded into memory at the same time and job scheduler selected a job (say job A)
  - If a big I/O request come for job A, then A's context is stored away and job B is started on the CPU
  - Once A's I/O finished, restore A

#### Multiprogramming: Issues

- Relies on the fact that job B can execute on the CPU when job A is doing I/O
  - Need to store context (current program state)
  - Need memory protection
  - Need privileged mode
- For multiprogramming to work: a good mix of CPU-bound and I/O-bound jobs
  - What if it is not the case?

#### Today's class

- A brief historical overview of OS
  - Batch processing systems
  - Multiprogramming
  - Multitasking
- Today's OS (multitasking, like Unix)
  - Dual mode of operation
  - Uses of timer

#### Multitasking (timesharing)

- Logical extension of multiprogramming
  - CPU switches jobs so fast that users can interact with each job while its running
  - Creates interactive computing (e.g., cancel an ongoing download, GUI)
- Characteristics
  - Real time: meeting deadline for jobs
  - Better share resources between jobs

#### Multitasking: Need for new tech

- Concept of CPU scheduling
  - Need hardware timers
  - Need scheduling algorithm (which task to allocate the CPU, out of all tasks that are ready to execute)
  - Have to worry about context switch overhead
  - Concept of CPU burst and I/O burst (lots of CPU operations OR lots of I/O operations in one go, so that context switches are minimized)

#### Today's class

- A brief historical overview of OS
  - Batch processing systems
  - Multiprogramming
  - Multitasking
- Today's OS (multitasking, like Unix)
  - Dual mode of operation
  - Uses of timer

#### Multitasking: The tools

- For multitasking, somebody needs to schedule the tasks as time goes
  - Kernel does it
  - Dual mode of operation
  - Use of timer

#### Dual mode of operation

- Process / task can execute in two modes
  - User mode and kernel mode (also called privileged mode)
  - User mode: run normal tasks
  - Kernel mode: directly talk to CPU/Peripherals to schedule tasks

#### Dual mode of operation

- Process / task can execute in two modes
  - User mode and kernel mode (also called privileged mode)
  - User mode: run normal tasks
  - Kernel mode: directly talk to CPU/Peripherals to schedule tasks
- Mode bit provided in hardware
  - Tells CPU if it is running in user or kernel mode

#### Kernel mode facilities

- Can run privileged instructions on CPU
  - Only in kernel mode
  - If you try to run them in user mode, generates exceptions
  - Examples: low-level I/O operation, setting protection registers, running EI, DI instructions (Enable/Disable interrupt)

### How to switch between these two modes?

System call or interrupt changes mode to kernel


Special "return" instruction changes mode to user


### How to switch between these two modes?


System call or interrupt changes mode to kernel


Special "return" instruction changes mode to user


But when to change modes when applications are running?











#### Today's class

- A brief historical overview of OS
  - Batch processing systems
  - Multiprogramming
  - Multitasking
- Today's OS (multitasking, like Unix)
  - Dual mode of operation
  - Uses of timer

#### How is hardware timer used?

- Recall that OS divide tasks into micro tasks and then schedule them in CPU
  - Uses a hardware timer to prevent infinite loop or resource hogging

#### How is hardware timer used?

- Recall that OS divide tasks into micro tasks and then schedule them in CPU
  - Uses a hardware timer to prevent infinite loop or resource hogging
- Timer is set such that it interrupts the processor after prespecified time
  - OS initializes the count value (privileged mode)
  - Count value in timer is decremented by physical clock
  - Timer generates an interrupt when count value is 0
  - Kernel "wakes up" upon interrupt and schedules next task