

Assignment:-4

Task 1:- Connect a USB webcam to your computer, install any required drivers, and verify that the webcam works by opening the default camera app and capturing a photo.

Steps to Test a USB Webcam

1. Connect the **USB webcam** to the computer.
2. Wait for Windows to **detect the webcam** and install the driver.
3. If needed, install the **webcam driver** from the manufacturer's website.
4. Open the **Camera app** from the Start menu.
5. Check that the webcam video appears on the screen.
6. Click the **Photo** button to take a picture.
7. Open the saved photo to **confirm that the webcam is working properly**.

Task 2:- Set up a local printer (USB or network), install the correct driver, and print a test page to confirm successful installation.

Steps to Set Up a Printer

1. **Connect the printer** — Connect it to the computer using a USB cable or connect it to the same Wi-Fi network.
2. **Turn on the printer** — Make sure the printer has paper and ink/toner.
3. **Open Settings** — Go to **Settings** → **Devices** → **Printers & scanners**.
4. **Add the printer** — Click **Add a printer or scanner** and select your printer.
5. **Install the driver** — Windows may install it automatically. If not, install the correct driver from the printer manufacturer's website.
6. **Set as default** — Select the printer and choose **Manage** → **Set as default**.
7. **Print a test page** — Choose **Manage** → **Print a test page**.
8. **Check the result** — If the page prints correctly, the printer is successfully installed.

Task 3:- Simulate a connectivity issue by unplugging the printer's USB cable, then use Windows Device Manager to identify and resolve the 'printer not detected' problem. Hint: Check for error icons and use the 'Scan for hardware changes' option after reconnecting.

Printer Not Detected – Simple Steps

1. Unplug the USB cable from the printer.
2. Open Device Manager on the computer.
3. Check Printers or Universal Serial Bus controllers for the printer.
4. Look for a yellow warning icon , which may show a problem.
5. Plug the USB cable back in firmly.
6. In Device Manager, click Action → Scan for hardware changes.
7. Check if the printer appears again without an error icon.
8. If it still does not appear, try another USB port and scan again.
9. Print a test page to confirm that the printer is working.

Task 4 :- user reports that their webcam video is not displaying in Zoom, but it works in the default camera app. Troubleshoot and resolve the issue so the webcam works in both applications. Hint: Check if another app is using the webcam or if Zoom permissions are enabled.

Webcam Problem in Zoom – Simple Steps

1. Close the Camera app — Make sure no other app is using the webcam.
2. Open Zoom — Go to Settings → Video.
3. Select the webcam — Choose the correct webcam from the camera list.
4. Check permissions — Go to Windows Settings → Privacy → Camera and allow camera access.
5. Allow Zoom access — Make sure desktop apps are allowed to access the camera.
6. Restart Zoom — Close Zoom completely and open it again.
7. Restart the computer — If the problem continues, restart the PC.
8. Test the webcam — Open Zoom and check that the video is now displaying