Day5 Review and Practice

Task 1:- Open Cisco Packet Tracer and create a new project file named 'HomeWiFiNetwork.pkt' with three PCs and one wireless router connected appropriately. send in simple steps

Steps to Create `HomeWiFiNetwork.pkt` in Cisco Packet Tracer

1. Open Cisco Packet Tracer on your computer.
2. Click File → New to create a new project.
3. From the bottom device panel, select End Devices.
4. Drag 3 PCs (PC0, PC1, PC2) into the workspace.
5. Select Wireless Devices and drag one Wireless Router into the workspace.
6. Connect the three PCs to the wireless router using Copper Straight-Through cables:
    - PC0 → Router Ethernet port 1
    - PC1 → Router Ethernet port 2
    - PC2 → Router Ethernet port 3
7. Click the wireless router and configure its wireless network:
    - SSID: `HomeWiFi`
    - Security: WPA2-PSK
    - Password: `Home@12345`
8. Click File → Save As.
9. Enter the file name `HomeWiFiNetwork.pkt`.
10. Select your desired folder and click Save.

Expected topology: One wireless router connected to three PCs using Ethernet cables.

Task 2:- Assign static IP addresses to each PC in your Packet Tracer network so they are on the same subnet (e.g., 192.168.10.x), and configure the default gateway to the router's IP.

Steps to Assign Static IP Addresses in Cisco Packet Tracer

Step 1: Configure the Wireless Router

1. Click the Wireless Router.
2. Open the GUI tab.
3. Go to Setup → Basic Setup.
4. Set the router's Local IP Address to `192.168.10.1`.
5. Set Subnet Mask to `255.255.255.0`.
6. Click Save Settings.

Step 2: Configure PC0

1. Click PC0.
2. Go to Desktop → IP Configuration.
3. Select Static.
4. Enter:
    - IP Address: `192.168.10.2`
    - Subnet Mask: `255.255.255.0`
    - Default Gateway: `192.168.10.1`

Step 3: Configure PC1

- IP Address: `192.168.10.3`
- Subnet Mask: `255.255.255.0`
- Default Gateway: `192.168.10.1`

Step 4: Configure PC2

- IP Address: `192.168.10.4`
- Subnet Mask: `255.255.255.0`
- Default Gateway: `192.168.10.1`

Step 5: Verify the Network

1. Open PC0 → Desktop → Command Prompt.
2. Type:

```
ping 192.168.10.1
```

3. To test communication with PC1, type:

```
ping 192.168.10.3
```

Expected result

You should receive successful ping replies if the connections and router settings are correct.

IP Address Table


Device	IP Address	Default Gateway
Router	192.168.10.1	—

Priyansh Bhaliya

PC0	192.168.10.2	192.168.10.1
PC1	192.168.10.3	192.168.10.1
PC2	192.168.10.4	192.168.10.1

Subnet Mask for all devices: `255.255.255.0`

Task 3:-Test connectivity by using the Packet Tracer 'ping' tool to verify that all PCs can communicate with each other and the router. Use the Command Prompt tool on each PC and type 'ping [other PC's IP]'.



Task 4:- Document each step you took to build and configure your Packet Tracer network, including screenshots of your topology and the IP configuration windows for each PC, Word



vlan and intervlan task steps.pdf