Tekushishikimime's Blog

UNCATEGORIZED

How to hack other computer using command prompt

<u>JUNE 19, 2015</u> | <u>TEKUSHISHIKIMIME</u> | <u>LEAVE A COMMENT</u>

THIS NETBIOS HACKING GUIDE WILL TELL YOU ABOUT HACKING REMOTE COMPUTER AND GAINING ACCESS TO IT'S HARD-DISK OR PRINTER. NETBIOS HACK IS THE EASIEST WAY TO BREAK INTO A REMOTE COMPUTER.

STEP-BY-STEP NETBIOS HACKING PROCEDURE

1. Open command prompt

2. In the command prompt use the "net view" command (OR YOU CAN ALSO USE "NB Scanner" OPTION IN "IP TOOLS" SOFTWARE BY ENTERING RANGE OF IP ADDRESSS. BY THIS METHOD YOU CAN SCAN NUMBER OF COMPUTERS AT A TIME).

Example: C:\>net view \\219.64.55.112

The above is an example for operation using command prompt. "net view" is one of the netbios command to view the shared resources of the remote computer. Here "219.64.55.112" is an IP address of remote computer that is to be hacked through Netbios. You have to substitute a vlaid IP address in it's place. If succeeded a list of HARD-DISK DRIVES & PRINTERS are shown. If not an error message is displayed. So repeat the procedure 2 with a different IP address.

3. After succeeding, use the "net use" command in the command prompt. The "net use" is another netbios command which makes it possible to hack remote drives or printers.

Example-1:

C:\>net use D: \\219.64.55.112\F

Example-2:

C:\>net use G: \\219.64.55.112\SharedDocs

Example-3:

C:\>net use I: \\219.64.55.112\Myprint

NOTE: In Examples 1,2 & 3, D:,G: & I: are the Network Drive Names that are to be created on your computer to access remote computer's hard-disk.

NOTE: GIVE DRIVE NAMES THAT ARE NOT USED BY ANY OTHER DRIVES INCLUDING HARD-DISK DRIVES, FLOPPY DRIVES AND ROM-DRIVES ON YOUR COMPUTER. THAT IS, IF YOU HAVE C: & D: AS HARD DIRVES, A: AS FLOPPY DIVE AND E: AS CD-DRIVE, GIVE F: AS YOUR SHARED DRIVE IN THE COMMAND PROMPT