Compte Rendue

Mission 1

Romain PICCOLI
HPK9

Table des matières

Configuration de l'AD/DNS 1
Création du domaine AD 2
Configuration SRV DNS 2
Configuration du serveur DHCP. 2
Configuration des étendues des vlan 2
Configuration du serveur BDD Debian 3
Création des enregistrements DNS pour la machine DEBIAN 3
Créer deux VM Windows 11 sur votre poste 3
Rattacher toutes les VM sur le domaine 4
Création des vlan 4
Création des sous-interfaces 4
Configuration routage inter-VLAN 5
Sauvegarde config 6

Nom machine	IP	vlan	port	VMID
PICCOLI-HPK-AD-DNS	172.16.91.1	409		209001
PICCOLI-HPK-DHCP	172.16.91.2	409		209002
PICCOLI-HPK-DEB13-01	172.16.91.4	409		209003
PICCOLI-HPK-PFSENSE LAN	172.18.91.1	209		209004
PICCOLI-HPK-PFSENSE WAN	172.20.109.253			

Configuration de l'AD/DNS



Configuration addressee IP: SRV-AD/DNS = 172.16.91.1 /24

Et modification du nom de l'ordinateur

Création du domaine AD



Configuration SRV DNS



Configuration du serveur DHCP.



Configuration des étendues des vlan



Configuration du serveur BDD Debian

209003 (PICCOLI-HPK-DB13)

Modification du nom de la machine :

hostnamectl et modification des fichiers hosts

Création des enregistrements DNS pour la machine DEBIAN




```
C:\Users\Administrateur>ping RPI-DNS

Envoi d'une requête 'ping' sur RPI-DNS.hpk9.labo [172.16.91.4] avec 32 octets de données :
Réponse de 172.16.91.4 : octets=32 temps<1ms TTL=64
Réponse de 172.16.91.4 : octets=32 temps<1ms TTL=64
Réponse de 172.16.91.4 : octets=32 temps<1ms TTL=64
Réponse de 172.16.91.4 : octets=32 temps<1ms TTL=64
```

```
# Generated by dhcpcd
# /etc/resolv.conf.head can replace this line
# /etc/resolv.conf.tail can replace this line
nameserver 172.16.91.1
```

Créer deux VM Windows 11 sur votre poste

Ils auront pour vocation de tester les vlan et les étendue DHCP



Rattacher toutes les VM sur le domaine



Création des vlan

Chaque vlan va correspondre au étendus DHCP,

```
VLAN Name                             Status    Ports
---- -------------------------------- --------- -------------------------------
1    default                          active    Fa0/15, Fa0/16, Fa0/17, Fa0/18
                                                Fa0/19, Fa0/20, Fa0/21, Fa0/22
                                                Fa0/24, Gi0/1, Gi0/2
9    VLAN0009                         active
10   VLAN0010                         active
29   sortie                           active    Fa0/23
49   Serveur                          active
91   Informatique                     active    Fa0/1, Fa0/2
92   Direction                        active    Fa0/3, Fa0/4
93   Developpement                    active    Fa0/5, Fa0/6
94   Commercial                       active    Fa0/7, Fa0/8
95   RH/Compta                        active    Fa0/9, Fa0/10
96   Support                          active    Fa0/11, Fa0/12
97   Visiteur                         active    Fa0/13, Fa0/14
1002 fddi-default                     act/unsup
1003 token-ring-default               act/unsup
1004 fddinet-default                  act/unsup
1005 trnet-default                    act/unsup
```

Création des sous-interfaces

Sur le router, il faut forcément paramétrer les sous interfaces

```
interface GigabitEthernet0/1.91
 encapsulation dot1Q 91
 ip address 192.168.91.254 255.255.255.0
 ip helper-address 172.16.91.2
!
```

```
interface GigabitEthernet0/1.209
 encapsulation dot1Q 209
 ip address 172.18.91.254 255.255.255.252
!
interface GigabitEthernet0/1.409
 encapsulation dot1Q 409
 ip address 172.16.91.254 255.255.255.0
```

Chaque sous interface (sauf 409 et 209)

Possède un IP helper pour permettre la redirection du service DHCP

Configuration routage inter-VLAN

Enfin, sur une VM Windows 11 on peut recevoir une IP dynamique et faire ping un autre poste en IP dynamique.

```
C:\Users\carriat>ping 192.168.94.2

Envoi d'une requête 'Ping'  192.168.94.2 avec 32 octets de données :
Réponse de 192.168.94.2 : octets=32 temps=1 ms TTL=127
Réponse de 192.168.94.2 : octets=32 temps=1 ms TTL=127
Réponse de 192.168.94.2 : octets=32 temps=1 ms TTL=127
Réponse de 192.168.94.2 : octets=32 temps<1ms TTL=127

Statistiques Ping pour 192.168.94.2:
    Paquets : envoyés = 4, reçus = 4, perdus = 0 (perte 0%),
Durée approximative des boucles en millisecondes :
    Minimum = 0ms, Maximum = 1ms, Moyenne = 0ms
```

Vérification des VLANs

```
C:\Users\carriat>ipconfig /all

Configuration IP de Windows

   Nom de l'hôte . . . . . . . . . . . : DESKTOP-TB33RE3
   Suffixe DNS principal . . . . . . . :
   Type de noeud. . . . . . . . . . . : Hybride
   Routage IP activé . . . . . . . . . : Non
   Proxy WINS activé . . . . . . . . . : Non

Carte Ethernet Ethernet0 :

   Suffixe DNS propre à la connexion. . . :
   Description. . . . . . . . . . . . . . : Intel(R) 82574L Gigabit Network Connection
   Adresse physique . . . . . . . . . . . : 00-0C-29-DC-9A-23
   DHCP activé. . . . . . . . . . . . . . : Oui
   Configuration automatique activée. . . : Oui
   Adresse IPv6 de liaison locale. . . . .: fe80::16dc:f062:50c7:cbfc%3(préféré)
   Adresse IPv4. . . . . . . . . . . . . .: 192.168.91.2(préféré)
   Masque de sous-réseau. . . . . . . . . : 255.255.255.0
   Bail obtenu. . . . . . . . . . . . . . : jeudi 18 décembre 2025 16:44:50
   Bail expirant. . . . . . . . . . . . . : vendredi 26 décembre 2025 16:45:05
   Passerelle par défaut. . . . . . . . . : 192.168.91.254
   Serveur DHCP . . . . . . . . . . . . . : 172.16.91.2
   IAID DHCPv6 . . . . . . . . . . . . . : 100666409
   DUID de client DHCPv6. . . . . . . . . : 00-01-00-01-30-67-11-71-00-0C-29-DC-9A-23
   Serveurs DNS. . .  . . . . . . . . . . : 172.16.91.1
   NetBIOS sur Tcpip. . . . . . . . . . . : Activé

C:\Users\carriat>
```

Sauvegarde config

Ne pas oublier de faire une sauvegarde de la conf switch et router

```
Router#copy running-config piccoli-hpk
Destination filename [piccoli-hpk]?
%Warning:There is a file already existing with this name
Do you want to over write? [confirm]
3385 bytes copied in 0.896 secs (3778 bytes/sec)
```

Compte Rendue

Mission 2

Romain PICCOLI
HPK9

Table des matières

Installation de pfSense 1
Mise en place des routes statiques vers les VLAN 1
Création des route-map 2
Configuration du redirecteur DNS 3
Ouvrir le port 3389 de l'IP SIO vers l'AD uniquement pour l'IP de l'étudiant 3
Rattacher le pfSense à l'AD 4
Création du certificat 4
Configurer le serveur Pfsene 5
Création d'un groupe VPN-USER sur l'AD avec des comptes 6
Configurer OpenVPN pour les utilisateurs du groupe VPN-USER 7
Création certificat ..... **Error! Bookmark not defined.**
Télécharger OpenVPN 13

Installation de pfSense



Mise en place des routes statiques vers les VLANs

Création des routes statiques sur pfsense

Route net -add address/24 pfsense

Création des route-map

Sur le routeur, faire :

Créer une access-list pour chaque réseau

Créer une route map avec la passerelle correspondante au réseau pour chaque réseau

Créer une sous-interface

Création des access-list

access-list 10 permit 192.168.91.0 0.0.0.255

access-list 10 permit 192.168.92.0 0.0.0.255

access-list 10 permit 192.168.93.0 0.0.0.255

access-list 10 permit 192.168.94.0 0.0.0.255

access-list 10 permit 192.168.95.0 0.0.0.255

access-list 10 permit 192.168.96.0 0.0.0.255

access-list 10 permit 192.168.97.0 0.0.0.255

access-list 10 permit 172.16.91.0 0.0.0.255

Création des route map

route-map RPIHPK09 permit

match ip address 10

set ip next-hop 172.18.91.1

Création des sous-interfaces

int g0/1.[SOUS_INTERFACE]

ip policy route-map RPIHPK09

Ne pas le faire sur l’interface 20x

Configuration du redirecteur DNS





Ouvrir le port 3389 de l'IP SIO vers l'AD uniquement pour l'IP de l'étudiant





Rattacher le pfSense à l'AD

Création du certificat

Sur L'AD faire :

```
Get-ChildItem -Path Cert:\LocalMachine\Root
```

Puis exporter le certificat de l'AD :

$cert = Get-ChildItem -Path Cert:\LocalMachine\Root\

Export-Certificate -Cert $cert -FilePath c:\ssl\root-ca-cert.cer -Type CERT

certutil -encode c:\ssl\root-ca-cert.cer c:\ssl\root-ca-cert.pem



(changer la photo)

Configurer le serveur Pfsene

System / User Manager / Authentication Servers

Users | Groups | Settings | Change Password | Authentication Servers

+ Add

Port value	636
Transport	SSL/TLS Encrypted
Peer Certificate Authority	certificat-root-CA This CA is used to validate the LDAP server certificate when 'SSL/TLS Encrypted' or 'STARTTLS Encrypted' Transport is active. This CA must matcl CA used by the LDAP server.
Protocol version	3
Server Timeout	25 Timeout for LDAP operations (seconds)
Search scope	Level Entire Subtree Base DN DC=hpk9,DC=labo
Authentication containers	CN=Users,DC=hpk9,DC=labo Note: Semi-Colon separated. This will be prepended to the search base dn above or the full container path can be specified containing a dc= component. Example: CN=Users;DC=example,DC=com or OU=Staff;OU=Freelancers Select a container
Extended query	☐ Enable extended query
Bind anonymous	☐ Use anonymous binds to resolve distinguished names
Bind credentials	CN=Pfsense,CN=Users,DC=hpk9,DC=labo ••••••••••••
User naming attribute	samAccountName
Group naming attribute	cn
Group member attribute	memberOf
RFC 2307 Groups	☐ LDAP Server uses RFC 2307 style group membership RFC 2307 style group membership has members listed on the group object rather than using groups listed on user object. Leave unchecked for Ac Directory style group membership (RFC 2307bis).



Si problème de résolution de nom

Custom options

```
server:
    local-zone: "hpk9.labo." transparent
    forward-zone:
        name: "hpk9.labo."
        forward-addr: 172.16.91.1
```

Création d'un groupe VPN-USER sur l'AD avec des comptes



Configurer OpenVPN pour les utilisateurs du groupe VPN-USER

Création certificat

Create / Edit CA

Descriptive name: AU-hpk-openvpn
The name of this entry as displayed in the GUI for reference.
This name can contain spaces but it cannot contain any of the following characters: ?, >, <, &, /, \, ", '

Method: Import an existing Certificate Authority

Trust Store: ☐ Add this Certificate Authority to the Operating System Trust Store
When enabled, the contents of the CA will be added to the trust store so that they will be trusted by the operating system.

Randomize Serial: ☐ Use random serial numbers when signing certificates
When enabled, if this CA is capable of signing certificates then serial numbers for certificates signed by this CA will be automatically randomized and checked for uniqueness instead of using the sequential value from Next Certificate Serial.

Existing Certificate Authority

Certificate data:
```
-----BEGIN CERTIFICATE-----
MIID9zCCAt+gAwIBAgIIcvm+uEhUNBYwDQYJKoZIhvcNAQELBQAwVj
ERMA8GA1UE
AxMISFBLOS12cG4xCzAJBgNVBAYTAkZSMQwwCgYDVQQIEwNBSU4xFz
AVBgNVBAcT
```
Paste a certificate in X.509 PEM format here.

Certificate Private Key (optional):
```
-----BEGIN PRIVATE KEY-----
MIIEvQIBADANBgkqhkiG9w0BAQEFAASCBKcwggSjAgEAAoIBAQDjiG
ON2Bt83nEB
wfTtivzzryo6naFaoYq1FZWeTCalozhxkybQFpL40iwlWRHbIM09hf
43Qmk+BqT8
```
Paste the private key for the above certificate here. This is optional in most cases, but is required when generating a Certificate Revocation List (CRL).

Next Certificate Serial: 3
Enter a decimal number to be used as a sequential serial number for the next certificate to be signed by this CA. This value is ignored when Randomize Serial is checked.

Save

Extended query: ☑ Enable extended query

Query: memberOf=CN=VPN-USER,CN=Users,DC=hpk9,DC=labo
Example (MSAD): memberOf=CN=Groupname,OU=MyGroups,DC=example,
Example (2307): |(&(objectClass=posixGroup)(cn=Groupname)(memberUid

Configuration open VPN


VPN / OpenVPN / Servers / Edit
Servers
Clients
Client Specific Overrides
Wizards
Client Export
General Information
Description
Openvpn-HPK09
A description of this VPN for administrative reference.
Disabled
Disable this server
Set this option to disable this server without removing it from the list.
Unique VPN ID
Server 1 (ovpns1)
Mode Configuration
Server mode
Remote Access (SSL/TLS + User Auth)
Backend for authentication
HPK-DC
Local Database
Device mode
tun - Layer 3 Tunnel Mode

Endpoint Configuration

Protocol: UDP on IPv4 only

Interface: WAN
The interface or Virtual IP address where OpenVPN will receive client connections.

Local port: 1194
The port used by OpenVPN to receive client connections.

Cryptographic Settings

TLS Configuration: [x] Use a TLS Key
A TLS key enhances security of an OpenVPN connection by requiring both parties to have a common key before a peer can perform a TLS handshake. This layer of HMAC authentication allows control channel packets without the proper key to be dropped, protecting the peers from attack or unauthorized connections.The TLS Key does not have any effect on tunnel data.

TLS Key:

```
#
# 2048 bit OpenVPN static key
#
-----BEGIN OpenVPN Static key V1-----
13e1336722995046ea22dd185edb854e
```

Paste the TLS key here.
This key is used to sign control channel packets with an HMAC signature for authentication when establishing the tunnel.

TLS Key Usage Mode: TLS Authentication
In Authentication mode the TLS key is used only as HMAC authentication for the control channel, protecting the peers from unauthorized connections. Encryption and Authentication mode also encrypts control channel communication, providing more privacy and traffic control channel obfuscation.

TLS keydir direction: Use default direction
The TLS Key Direction must be set to complementary values on the client and server. For example, if the server is set to 0, the client must be set to 1. Both may be set to omit the direction, in which case the TLS Key will be used bidirectionally.

Peer Certificate Authority: AU-hpk-openvpn

Peer Certificate Revocation list: No Certificate Revocation Lists defined. One may be created here: System > Cert. Manager

OCSP Check: [ ] Check client certificates with OCSP

Server certificate: VPN-SSL-REMOTE-ACCESS (Server: Yes, CA: AU-hpk-openvpn, In U:
Certificates known to be incompatible with use for OpenVPN are not included in this list, such as certificates using incompatible ECDSA curves or weak digest algorithms.

DH Parameter Length: 2048 bit
Diffie-Hellman (DH) parameter set used for key exchange.

ECDH Curve: Use Default
The Elliptic Curve to use for key exchange.
The curve from the server certificate is used by default when the server uses an ECDSA certificate. Otherwise, secp384r1 is used as a fallback.

IPv4 Tunnel Network	10.10.10.0/24 This is the IPv4 virtual network or network type alias with a single entry used for private communications between this server and client hosts expressed using CIDR notation (e.g. 10.0.8.0/24). The first usable address in the network will be assigned to the server virtual interface. The remaining usable addresses will be assigned to connecting clients. A tunnel network of /30 or smaller puts OpenVPN into a special peer-to-peer mode which cannot push settings to clients. This mode is not compatible with several options, including Exit Notify, and Inactive.
IPv6 Tunnel Network	This is the IPv6 virtual network or network type alias with a single entry used for private communications between this server and client hosts expressed using CIDR notation (e.g. fe80::/64). The ::1 address in the network will be assigned to the server virtual interface. The remaining addresses will be assigned to connecting clients.
Redirect IPv4 Gateway	☐ Force all client-generated IPv4 traffic through the tunnel.
Redirect IPv6 Gateway	☐ Force all client-generated IPv6 traffic through the tunnel.
IPv4 Local network(s)	172.16.91.0/24,192.168.91.0/24,192.168.92.0/24,192.168.93.0/24 IPv4 networks that will be accessible from the remote endpoint. Expressed as a comma-separated list of one or more CIDR ranges or host/network type aliases. This may be left blank if not adding a route to the local network through this tunnel on the remote machine. This is generally set to the LAN network.
IPv6 Local network(s)	IPv6 networks that will be accessible from the remote endpoint. Expressed as a comma-separated list of one or more IP/PREFIX or host/network type aliases. This may be left blank if not adding a route to the local network through this tunnel on the remote machine. This is generally set to the LAN network.
Concurrent connections	10 Specify the maximum number of clients allowed to concurrently connect to this server.

Client Settings

Dynamic IP	☑ Allow connected clients to retain their connections if their IP address changes.
Topology	net30 – Isolated /30 network per client Specifies the method used to supply a virtual adapter IP address to clients when using TUN mode on IPv4. Some clients may require this be set to "subnet" even for IPv6, such as OpenVPN Connect (iOS/Android). Older versions of OpenVPN (before 2.0.9) or clients such as Yealink phones may require "net30".

Ping settings

Inactivity Timeout	300 Causes OpenVPN to close a client connection after n seconds of inactivity on the TUN/TAP device. Activity is based on the last incoming or outgoing tunnel packet. A value of 0 disables this feature. This option is ignored in Peer-to-Peer Shared Key mode and in SSL/TLS mode with a blank or /30 tunnel network as it will cause the server to exit and not restart.
Ping method	keepalive – Use keepalive helper to define ping configuration keepalive helper uses interval and timeout parameters to define ping and ping-restart values as follows: ping = interval ping-restart = timeout*2 push ping = interval push ping-restart = timeout
Interval	10
Timeout	60

Advanced Client Settings

DNS Default Domain	☑ Provide a default domain name to clients
DNS Default Domain	PICCOLI-HPK-AD-DNS.labo
DNS Server enable	☑ Provide a DNS server list to clients. Addresses may be IPv4 or IPv6.
DNS Server 1	172.16.91.1

System / Package Manager / Installed Packages

Installed Packages | Available Packages

Installed Packages

	Name	Category	Version	Description	Actions
	openvpn-client-export	security	1.9.5	Exports pre-configured OpenVPN Client configurations directly from pfSense software. Package Dependencies: openvpn-client-export-2.6.7 openvpn-2.6.14 zip-3.0_3 7-zip-24.09	

= Update = Current
= Remove = Information = Reinstall
Newer version available
Package is configured but not (fully) installed or deprecated

Search

Search term [ ] Search Clear

Enter a search string or *nix regular expression to search.

OpenVPN Clients

User	Certificate Name	Export
Certificate with External Auth	VPN-HPK	- Inline Configurations: Most Clients Android OpenVPN Connect (iOS/Android) - Bundled Configurations: Archive Config File Only - Current Windows Installer (2.6.7-Ix001): 64-bit 32-bit - Previous Windows Installer (2.5.9-Ix601): 64-bit 32-bit - Legacy Windows Installers (2.4.12-Ix601): 10/2016/2019 7/8/8.1/2012r2 - Viscosity (Mac OS X and Windows): Viscosity Bundle Viscosity Inline Config

Bureau > pfSense-UDP4-1194-user-vpn

Trier Afficher ...

Nom	Modifié le	Type	Taille
pfSense-UDP4-1194-user-vpn.ovpn	04/12/2025 14:35	OVPN Profile	1 Ko
pfSense-UDP4-1194-user-vpn.p12	04/12/2025 14:35	Échange d'inform...	5 Ko
pfSense-UDP4-1194-user-vpn-config.ovpn	04/12/2025 15:21	OVPN Profile	6 Ko
pfSense-UDP4-1194-user-vpn-tls.key	04/12/2025 14:35	Fichier KEY	1 Ko



Puis créer une nouvelle règle sur le firewall





Télécharger OpenVPN



Nom	Modifié le	Type	Taille
pfSense-UDP4-1194-user-vpn.ovpn	04/12/2025 14:35	OVPN Profile	1 Ko
pfSense-UDP4-1194-user-vpn.p12	04/12/2025 14:35	Échange d'inform...	5 Ko
pfSense-UDP4-1194-user-vpn-config.ovpn	04/12/2025 15:21	OVPN Profile	6 Ko
pfSense-UDP4-1194-user-vpn-tls.key	04/12/2025 14:35	Fichier KEY	1 Ko

Users-vpn

Carriat_2025


OpenVPN Connect
Securely Connected!
00:00:23
172.20.109.253 [pfSense-...
172.20.109.253
Disconnect
4.11 KB/s
40 B/s
0 KB/s
~0 sec ago
More Details

Installation de TrueNas



Configuration de l'interface en HTTPS



Création d'un partage SMB, FTP et TFTP

Créer le pool RAID



Création d'un partage SMB, FTP et TFTP



Puis ne pas oublier de l’activer si nécessaire



Connexion à l'AD

Dans Network → Global Configuration → settings



Teste : nslookup mondomaine.local

Ensuite dans **System** → **General settings** → **NTP Servers**

NTP Servers

Address	Burst	IBurst	Prefer	Min Poll	Max Poll
0.debian.pool.ntp.org	No	Yes	No	6	10
1.debian.pool.ntp.org	No	Yes	No	6	10
2.debian.pool.ntp.org	No	Yes	No	6	10
172.16.91.1	No	Yes	No	6	10

Ensuite tester : ping mondomaine.local

Enfin dans **Credentials** → **Directory Services**

Ajouter un serveur AD mettre le domaine HPK9.labo l'utilisateur Administrateur et MDP

Directory Services

Active Directory

Settings

Status: HEALTHY

Domain Name: HPK9.LABO

Domain Account Name: administrateur

Modifier les droits sinon il y aura « **Windows ne peut pas accéder à \truenas\smb_ds** » donc dans **Datasets** → **Permissions**→ **edit**



Maintenant il est possible d’avoir accès aux fichiers SMB-DS

- BDD : Installer PosteGreSQL

Apt install PosteGreSQL

- BDD : Installation PhpPgAdmin

Apt install PhpPgAdmin

- BDD : Création de l'utilisateur Odoo

su postgres

psql

```
root@mod-d13:~# su postgres
postgres@mod-d13:/root$ psql
psql (17.6 (Debian 17.6-0+deb13u1))
Saisissez « help » pour l'aide.

postgres=#
```

```
postgres=# create user odoo with password 'carriat';
CREATE ROLE
postgres=# alter user odoo createdb ;
ALTER ROLE
postgres=#
```

```
postgres=# create database odoo owner odoo;
CREATE DATABASE
```

Autoriser connexions distantes

Modifier :

nano /etc/postgresql/*/main/pg_hba.conf

Ajouter :

host all all 172.16.91.0/24 md5

Modifier :

nano /etc/postgresql/*/main/postgresql.conf

listen_addresses = '*'

systemctl restart postgresql

```
host    all             all             0.0.0.0/0               md5



root@mod-d13:~# systemctl restart postgresql
root@mod-d13:~# nano /etc/postgresql/*/main/pg_hba.conf_
```

- ERP1(ODOO1) : Installation Odoo avec la BDD du serveur BDD

Sur la VM Odoo :

apt install python3-venv python3-pip git

Installation Odoo

mkdir /opt/odoo19
cd /opt/odoo19
git clone https://www.github.com/odoo/odoo --depth 1 --branch 19.0 .

python3 -m venv venv
source venv/bin/activate
pip install -r requirements.txt
deactivate

Configuration Odoo

nano /etc/odoo.conf

[options]
admin_passwd = carriat
db_host = 172.16.91.4
db_port = 5432
db_user = odoo
db_password = carriat
addons_path = /opt/odoo19/addons
proxy_mode = True

Lancement Odoo

```
cd /opt/odoo19
source venv/bin/activate
./odoo-bin -c /etc/odoo.conf -d odoo19 --init=base
```

Service Odoo

```
nano /etc/systemd/system/odoo.service
```

```
[Unit]
Description=Odoo
After=network.target

[Service]
User=odoo
ExecStart=/opt/odoo19/venv/bin/python3 /opt/odoo19/odoo-bin -c /etc/odoo.conf

[Install]
WantedBy=multi-user.target
```

```
systemctl daemon-reexec
systemctl enable odoo
systemctl start odoo
```

Clone ERP2

Clone de la VM ODOO1
Changement IP (ex: 172.16.91.8)
Autorisation dans PostgreSQL déjà faite

Serveur WEB (NGINX)

Installation NGINX

```
apt install nginx
```

Creation du certificat SSL auto-signé

```
mkdir -p /etc/nginx/ssl/odoo
```

```
openssl req -x509 -nodes -days 365 -newkey rsa:2048 \
-keyout /etc/nginx/ssl/odoo/odoo.key \
-out /etc/nginx/ssl/odoo/odoo.crt
```

Permet d’activer HTTPS

Configuration NGINX

nano /etc/nginx/sites-available/odoo

```
upstream odoo_backend {
    ip_hash; # important pour odoo
    server 172.16.91.6:8069;
    server 172.16.91.8:8069;
}

server {
    listen 80;
    server_name odoo.hpk.local;
    return 301 https://$host$request_uri;
}

server {
    listen 443 ssl;
    server_name odoo.hpk.local;

    ssl_certificate /etc/nginx/ssl/odoo.crt;
    ssl_certificate_key /etc/nginx/ssl/odoo.key;

    location / {
        proxy_pass http://odoo_backend;
        proxy_set_header Host $host;
        proxy_set_header X-Real-IP $remote_addr;
        proxy_set_header X-Forwarded-For $proxy_add_x_forwarded_for;
        proxy_set_header X-Forwarded-Proto https;
    }
}
```

Reverse proxy + HTTPS + load balancing

Activation du site

ln -s /etc/nginx/sites-available/odoo /etc/nginx/sites-enabled/

systemctl restart nginx



Sur le PC client :

Modifier fichier hosts :

172.16.91.7 odoo.hpk.local

Accès :

https://odoo.hpk.local