

```
#!/bin/bash

display_env() {
    echo "Current Environment Variables:"
    printenv
}

set_env() {
    read -p "Enter variable name: " name
    read -p "Enter variable value: " value
    export $name=$value
    echo "Variable $name set successfully."
}

show_env() {
    echo "Environment variables using env command:"
    env
}

while true
do
    echo "----- Environment Variable Manager -----"
    echo "1. Display variables (printenv)"
    echo "3. Display variables (env)"
    echo "4. Exit"
    read -p "Enter choice: " ch
    case $ch in
        1) display_env ;;
        2) set_env ;;
        3) show_env ;;
        4) exit ;;
        *) echo "Invalid choice" ;;
    esac
done
```

```
(base) rvu@rvu-OptiPlex-SFF-7020:~/raghavendra$ nano blah.sh
(base) rvu@rvu-OptiPlex-SFF-7020:~/raghavendra$ ./blah.sh
----- Environment Variable Manager -----
1. Display variables (printenv)
3. Display variables (env)
4. Exit
Enter choice: 2
Enter variable name: MYVAR
Enter variable value: HelloWorld
Variable MYVAR set successfully.
----- Environment Variable Manager -----
1. Display variables (printenv)
3. Display variables (env)
4. Exit
Enter choice: 1
Current Environment Variables:
SHELL=/bin/bash
SESSION_MANAGER=local/rvu-OptiPlex-SFF-7020:@/tmp/.ICE-unix/2411,unix/rvu-OptiPlex-SFF-7020:/tmp/.ICE-unix/2411
QT_ACCESSIBILITY=1
COLORTERM=truecolor
XDG_CONFIG_DIRS=/etc/xdg/xdg-ubuntu:/etc/xdg
XDG_MENU_PREFIX=gnome-
GNOME_DESKTOP_SESSION_ID=this-is-deprecated
CONDA_EXE=/home/rvu/anaconda3/bin/conda
__CE_M=
MYVAR=HelloWorld
GNOME_SHELL_SESSION_MODE=ubuntu
SSH_AUTH_SOCK=/run/user/1000/keyring/ssh
MEMORY_PRESSURE_WRITE=c29tZSAyMDAwMDAgMjAwMDAwMAA=
XMODIFIERS=@im=ibus
DESKTOP_SESSION=ubuntu
GTK_MODULES=gail:atk-bridge
PWD=/home/rvu/raghavendra
GSETTINGS_SCHEMA_DIR=/home/rvu/anaconda3/share/glib-2.0/schemas
XDG_SESSION_DESKTOP=ubuntu
LOGNAME=rvu
```