Radium Wallet Instructions

Downloading

You can download the last version of Radium wallet from official site: https://radiumcore.org

Wallets for latest version of Windows, MacOS, Ubuntu are available here:
https://radiumcore.org/downloads

Installing

- Open the downloaded exe file
- When you first install the wallet your will be prompted by the Windows firewall to give the program permission. Simply hit *Allow access*
- Your wallet will now begin to synchronize with the network
- When your wallet has completed synchronizing with the network you will see the following symbol:

Encrypting your wallet

- Go to Settings
- Click on Encrypt wallet
- Put in a strong passphrase that you can remember

Making a back-up

- Go to file
- Click on Backup Wallet
- Save the file with the extension .dat

Restoring a back-up (Windows)

- Close your wallet
- Search for the folder: %APPDATA%\Radium (press Win+R, insert %APPDATA%\Radium and press Enter, it will open your local Radium folder for your current user)
- Remove the wallet.dat file in the folder
- Put your back up .dat file in the folder and name it wallet.dat
- Open your wallet
- NEVER DELETE THE WALLET.DAT FILE

Restoring a back-up (Mac)

- Close your wallet
- Search for the folder: ~/Library/Application Support/radium/

- Remove the wallet.dat file in the folder
- Put your back up .dat file in the folder and name it wallet.dat
- Open your wallet
- NEVER DELETE THE WALLET.DAT FILE

Staking

- Open your wallet
- Go to Settings
- Click on Unlock wallet

- Fill in your passphrase
- Click the box ''For staking only'' and press OK

To check if your wallet is staking correctly:

- First check if your wallet is encrypted and currently unlocked by moving your mouse on to the lock symbol, it should look like this:

- Second check if your wallet is staking by moving your mouse on to the lightning bolt:

- And last check your active connections, by moving your mouse on to the third symbol

When you have one active connection to the Radium network, you can add more connections through the following steps:

- Close your wallet
- Search for the folder: %APPDATA%\Radium
- Open note pad and add the following text (see attachment 1 Node list)
- Save the file as radium.conf (make sure the file is not saved as a .txt file) you should see an ''all file'' option when saving the conf file
- Drag the radium.conf file into your Radium folder
- Open your wallet and check your connections

Attachment 1 Node list could be found in the link below:

https://chainz.cryptoid.info/rads/#!network

Open it you can find the list of current working Sub-version of Radium clients, choose your version of client and press the button "node list", for example for 1.4.7:

Node List for /Radium:1.4.7/

Seen by explorer wallet in the last 24hours:

```
addnode=108.77.80.39
addnode=110.54.153.157
addnode=110.54.157.71
addnode=124.197.89.53
addnode=138.75.154.28
addnode=146.158.122.152
addnode=173.230.186.109
addnode=173.239.228.23
addnode=178.252.127.220
addnode=178.85.55.200
addnode=180.190.88.199
addnode=188.22.117.249
addnode=188.22.218.47
addnode=198.16.229.57
addnode=198.46.110.198
addnode=198.53.141.233
```

Select all strings from here and insert in file radium.conf