```
1 /*
    Vcc - A supply voltage measuring library for Arduino
 2
 3
 4
     Created by Ivo Pullens, Emmission, 2014
 5
     Inspired by:
 6
 7
     http://provideyourown.com/2012/secret-arduino-voltmeter-measure-battery-voltage/
8
9
     This library is free software; you can redistribute it and/or
     modify it under the terms of the GNU Lesser General Public
10
11
     License as published by the Free Software Foundation; either
12
     version 2.1 of the License, or (at your option) any later version.
13
    This library is distributed in the hope that it will be useful,
14
15
     but WITHOUT ANY WARRANTY; without even the implied warranty of
    MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU
16
    Lesser General Public License for more details.
17
18
19
    You should have received a copy of the GNU Lesser General Public
    License along with this library; if not, write to the Free Software
20
     Foundation, Inc., 51 Franklin St, Fifth Floor, Boston, MA 02110-1301 USA
21
22 */
23
24 #ifndef VCC H
25 #define VCC H
27 #include "Arduino.h"
28
29 class Vcc
30 {
31
     public:
       /**
32
33
        * Constructor
34
35
        * @param correction Correction factor, when reported Vcc is off from measured
   (externally) Vcc
36
                             (due to variations in bandgap voltage of +/- 0.1V)
        *
37
                             Calculate as Vcc measured/Vcc reported. Defaults to 1.
38
39
       Vcc( const float correction = 1.0 );
40
41
       * Retrieve current Vcc level.
42
43
44
        * @return Current Vcc level, in Volts.
45
46
       float Read_Volts(void);
47
48
49
       * Retrieve current Vcc level.
50
       * @return Current Vcc level, in milivolts.
51
52
53
       uint16_t Read_Volts_fast(void);
54
55
       /**
       * Retrieve current Vcc level. The total voltage range shall be passed
56
       * as low/high bound. For e.g. an alkaline AA battery this range can be set
57
58
        * to [0.6,..,1.5] Volts.
59
60
        * @param range_min Low bound to Vcc level range, in Volts.
```

```
61
      * @param range_max High bound to Vcc level range, in Volts.
      * @param clip
                  When set, assures returned percentage is clipped to
62
  [0..100]% range.
      * @return Current Vcc level, as percentage of expected Vcc level.
63
64
65
     float Read_Perc(const float range_min = 0.0, const float range_max = 0.0, const
  boolean clip = true);
66
67
   protected:
     68
69 };
70
71 #endif
```