Final Server Steps

Guide

This article is part of the Installation Guide. You can read it alone or click on the previous link to easily move between the steps.

<<Step 5: Networking

Step 7: Client Setup >>

After completing all the steps listed above you can now start your server.

- Run the authserver (bnetserver on master) to run your server.
 - Tip: The authserver (bnetserver on master) allows you to enter your username (email on master)/password to connect to the Realm Selection screen, and the worldserver allows you to connect to the realm itself. Once you are in-game, the authserver (bn etserver on master) can be safely closed if you wish no one else to connect to server.

<u>!NEVER!</u> create an account directly into your database unless you are ABSOLUTELY SURE that you know what to do and how to do it!

- Next create your Login Account by typing directly into the worldserver window the GM Command account create (bnetaccount create on master). Syntax: (see examples below)
- If you wish to set the account as a GM then type into the worldserver window: account set gmlevel \$account #level #realmid where \$
 account is the account name to change, #level can be 0-3 and #realmid is the realm ID. Setting a #level of "3" is GM account level
 (higher numbers = more access), and the "-1" is the realm ID that stands for "all realms".

Open the **world** database in your database management tool and find the **command** table. This table shows a full list of GM commands, their descriptions, and the security (GM level) needed to use them. You will not find a more accurate list of current GM commands anywhere else (assuming you keep your database up-to-date). The security level for a given command identifies that THAT GM level can use the command, along with all GM levels above it. For example, if a command has a security of 2, all accounts with a GM level of 2, 3, and 4 will be able to use it. More detailed information can be found at GM Commands Page.

- · Minimize your servers and run WoW (never run WoW using the Launcher unless you edited the realmlist.wtf's patchlist option above).
- · Log in using the user/pass you just created.
- The **Trinity** realm should be selectable. Log in, create a character, and you're all done!

Account Creation Examples:

3.3.5

To create your account: very important, don't use @ on account names.

Type: account create <user> <pass>

Example: account create test test

To set your account level:

Type: account set gmlevel <user> 3 -1

Example: account set gmlevel test 3 -1

Login to your account:

Log in with account test and password test through wow.exe.

master

To create your account:

Type: bnetaccount create <user> <pass>

Example: bnetaccount create test@test test

To set your account level:

Type: account set gmlevel <user#realm> 3 -1

Example: account set gmlevel 1#1 3 -1

Note: The **username** used for setting your **gmlevel** is **not the same as** the **username** you create with **bnetaccount**. You must manually **find** the **username in auth.account.username**. These are formatted as **1#1**, **2#1**, **etc.**

NOTE2: if you have connected before using this command you will need to relog.

Login to your account:

Log in with email test@test and password test.through Wow_Patched.exe or Wow-64_Patched.exe.

Guide

This article is part of the Installation Guide. You can read it alone or click on the previous link to easily move between the steps.

<<Step 5: Networking

Step 7: Client Setup >>