



Account Creation

Account Creation Form

To access the account creation form, go to the "Requests" page and access the "Service Principal" tab.

The screenshot shows the 'Requests' page with the 'Service Principal' tab selected. The 'Create new' button is highlighted with a red box. The page displays account details for 'Koh Jun Wei (GOVTECH)' and a table of requests.

System name	Data request(s)	Requested on	Status
GOVTECH SYSTEM 1	GOVTECH-2022-10-017	03 Mar 2025, 02:30 PM	0 / 1 Connections
GOVTECH SYSTEM 323	GOVTECH-2022-10-017	03 Mar 2025, 02:30 PM	Pending Approval

You will be redirected to the account creation form.

The screenshot shows the 'Service Principal Account Creation' form. The form includes sections for 'Instructions', 'Team Details', 'System Description', and 'Use case'. The 'Team Details' section has a text input for emails and a table for permissions. The 'System Description' section has inputs for system name and CDO. The 'Use case' section has a text input for the use case. The 'Submit' button is highlighted in blue.

Instructions

Please have your public key ready before you fill this form. Details to generate it can be found in our documentation [here](#). DataHive (support@datahive.gov.sg) will respond with the service principal details or if we require more information

Team Details

Enter or paste emails separated by a comma

Email	Permissions
koh_jun_wei@tech.gov.sg	Manage

System Description

System name

Name of system

System's CDO

Select CDO of the system

Use case

Input use case

Buttons: Cancel, Submit

Form Details

Team details

Enter the email of your team that will be required to manage or view this service principal account. There are 2 permissions that they can be assigned to:

Permissions	Description
Read-Only	The user can only read the details of the service principal account.
Manage	The user can read and make changes to the service principal account. For example, they can change the system's IP address, public key and request for more connections of the same type.

Types of System Connections

Currently, there are two types of connections you can set up:

Type	What it's for
Data Request Connection	Lets your system download data from approved Data Requests.
Tenant Connection	Lets your system upload files to datasets under a specific Tenant.

Public Key

A keypair is required to be used as an authentication mechanism for the service principal account.

! INFO

Only the public key is to be sent to DataHive for the provisioning of the service principal account.

Generate Private Key

To start, open a terminal window. If you are using a Windows machine, open a Git Bash terminal.

To generate an encrypted private key, use the following command and replace

<YourPassphraseHere> with a passphrase of your choice. This command will generate a private key `rsa_key.p8` in PEM format.

```
openssl genrsa -aes256 -passout pass:<YourPassphraseHere> -out rsa_key.p8 2048
```

Generate Public Key

From the command line, generate the public key by referencing the private key. The following command assumes the private key is encrypted and contained in the file named `rsa_key.p8`.

Replace <YourPassphraseHere> with the passphrase you just used for generating your private key. The command generates the public key `rsa_key.pub` in PEM format.

```
openssl rsa -in rsa_key.p8 -pubout -out rsa_key.pub -passin pass:  
<YourPassphraseHere>
```

Input/Upload this public key into the "Public Key 1" field.