



# Experiment 2.3

Student Name: Rajiv Paul UID: 20BCS1812

Branch: CSE Section/Group:607A

Semester: 4th Date of Performance: 04/04/2022

**Subject Name: Computer Networking Lab Subject Code: 22E-20CSP-257** 

1) Aim/Overview of the practical:

Create a network to implement Distance Vector routing Protocol using Packet Tracer.

2) Task to be done/ Which logistics used:

To create a network to implement Distance Vector routing Protocol using Packet Tracer.

**Cisco Packet Tracer** 







# 3) Steps for experiment/practical/Code:

- 1.Developed a topology of network.
- 2. Configured all the Routers and PCs.
- 3.Implemented RIP protocols in router to configure network

## Router0:

Router>enable

Router#

Router#configure terminal

Enter configuration commands, one per line. End with CNTL/Z.

Router(config)#interface FastEthernet0/0

Router(config-if)#ip address 192.168.10.2 255.255.255.0

Router(config-if)#ip address 192.168.10.1 255.255.255.0

Router(config-if)#no shutdown

Router(config-if)#

%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

Router(config-if)#







Router(config-if)#exit

Router(config)#interface Serial2/0

Router(config-if)#ip address 10.0.0.2 255.0.0.0

Router(config-if)#clock rate 64000

This command applies only to DCE interfaces

Router(config-if)#no shutdown

Router(config-if)#

%LINK-5-CHANGED: Interface Serial2/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0, changed state to up

Router(config-if)#

Router(config-if)#exit

Router(config)#router rip

Router(config-router)#network 192.168.10.0

Router(config-router)#network 10.0.0.0

Router(config-router)#

Router(config-router)#







#### Router 1:

Router>enable

Router#

Router#configure terminal

Enter configuration commands, one per line. End with CNTL/Z.

Router(config)#interface FastEthernet0/0

Router(config-if)#ip address 192.168.20.1 255.255.255.0

Router(config-if)#ip address 192.168.20.1 255.255.255.0

Router(config-if)#

Router(config-if)#

Router(config-if)#exit

Router(config)#interface FastEthernet0/0

Router(config-if)#no shutdown

Router(config-if)#

%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

Router(config-if)#

Router(config-if)#exit

Router(config)#interface Serial2/0

Router(config-if)#ip address 10.0.0.3 255.0.0.0

Router(config-if)#clock rate 64000

Router(config-if)#no shutdown

Router(config-if)#

%LINK-5-CHANGED: Interface Serial2/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0, changed state to up

Router(config-if)#exit

Router(config)#interface Serial3/0

Router(config-if)#ip address 20.0.0.2 255.0.0.0

Router(config-if)#ip address 20.0.0.2 255.0.0.0

Router(config-if)#clock rate 64000

Router(config-if)#no shutdown

Router(config-if)#

Router(config-if)#exit

Router(config)#interface Serial2/0







Router(config-if)#

Router(config-if)#

Router(config-if)#exit

Router(config)#router rip

Router(config-router)#network 192.168.20.0

Router(config-router)#network 10.0.0.0

Router(config-router)#

Router(config-router)#

Router(config-router)#end

Router#configure terminal

Enter configuration commands, one per line. End with CNTL/Z.

Router(config)#router rip

Router(config-router)#

%SYS-5-CONFIG\_I: Configured from console by console

network 20.0.0.0

Router(config-router)#

%LINK-5-CHANGED: Interface Serial3/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/0, changed state to up

%LINK-3-UPDOWN: Interface Serial3/0, changed state to down

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/0, changed state to down

Router(config-router)#

Router(config-router)#end

Router#configure terminal

Enter configuration commands, one per line. End with CNTL/Z.

Router(config)#interface Serial3/0

Router(config-if)#

%SYS-5-CONFIG\_I: Configured from console by console







#### **Router 2:**

Router>enable

Router#

Router#configure terminal

Enter configuration commands, one per line. End with CNTL/Z.

Router(config)#interface FastEthernet0/0

Router(config-if)#ip address 192.168.30.1 255.255.255.0

Router(config-if)#ip address 192.168.30.1 255.255.255.0

Router(config-if)#no shutdown

Router(config-if)#

%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

Router(config-if)#

Router(config-if)#exit

Router(config)#interface Serial3/0

Router(config-if)#ip address 20.0.0.3 255.0.0.0

Router(config-if)#clock rate 64000

Router(config-if)#no shutdown

Router(config-if)#

Router(config-if)#

Router(config-if)#exit

Router(config)#router rip

Router(config-router)#

Router(config-router)#

Router(config-router)#end

Router#configure terminal

Enter configuration commands, one per line. End with CNTL/Z.

Router(config)#router rip

Router(config-router)#

%SYS-5-CONFIG\_I: Configured from console by console

network 192.168.30.0

Router(config-router)#network 20.0.0.0

Router(config-router)#

Router(config-router)#end

Router#configure terminal

Enter configuration commands, one per line. End with CNTL/Z.







Router(config)#interface FastEthernet0/0

Router(config-if)#

%SYS-5-CONFIG I: Configured from console by console

Router(config-if)#exit

Router(config)#interface Serial2/0

Router(config-if)#

Router(config-if)#exit

Router(config)#interface Serial3/0

Router(config-if)#ip address 20.0.0.3 255.0.0.0

Router(config-if)#shutdown

Router(config-if)#ip address

% Incomplete command.

Router(config-if)#

Router(config-if)#exit

Router(config)#interface Serial2/0

Router(config-if)#ip address 20.0.0.3 255.0.0.0

Router(config-if)#ip address 20.0.0.3 255.0.0.0

Router(config-if)#clock rate 64000

This command applies only to DCE interfaces

Router(config-if)#no shutdown

Router(config-if)#

%LINK-5-CHANGED: Interface Serial2/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0, changed state to up

Router(config-if)#exit

Router(config)#router rip

Router(config-router)#no network 20.0.0.0

Router(config-router)#

Router(config-router)#end

Router#configure terminal

Enter configuration commands, one per line. End with CNTL/Z.

Router(config)#interface Serial2/0

Router(config-if)#

%SYS-5-CONFIG\_I: Configured from console by console

shutdown

Router(config-if)#clock rate 64000

This command applies only to DCE interfaces







Router(config-if)#

%LINK-5-CHANGED: Interface Serial2/0, changed state to administratively down

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0, changed state to down

Router(config-if)#exit

Router(config)#router rip

Router(config-router)#network 20.0.0.0

Router(config-router)#

Router(config-router)#

Router(config-router)#end

Router#configure terminal

Enter configuration commands, one per line. End with CNTL/Z.

Router(config)#interface Serial2/0

Router(config-if)#

%SYS-5-CONFIG\_I: Configured from console by console

no shutdown

Router(config-if)#

%LINK-5-CHANGED: Interface Serial2/0, changed state to up

Router(config-if)#exit

Router(config)#interface Serial3/0

Router(config-if)#

Router(config-if)#exit

Router(config)#interface FastEthernet0/0

Router(config-if)#


%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0, changed state to up








# 4. Result/Output/Writing Summary:










## **Outcome:**







# **Learning outcomes (What I have learnt):**

- 1. Learnt about Cisco Packet Tracer.
- 2. Learnt how the packets are transferred/travels.
- 3. Learnt about RIP routing.
- 4. Learnt about static routing.
- 5. Learnt how to configure routers.





# **Evaluation Grid (To be created as per the SOP and Assessment guidelines by the faculty):**

Sr. No.	Parameters	Marks Obtained	Maximum Marks
1.			
2.			
3.			

