OpenAS2

OpenAS2 is a java-based implementation of the EDIINT AS2 standard. It is intended to be used as a server. It is extremely configurable and supports a wide variety of signing and encryption algorithms.

Requirements:

- Java 1.8 or newer
- Any OS that run Java

Planned enhancements in the next major release:

- User interace configuration GUI
- Certificate Exchange Management

IMPORTANT: Java 1.7 is no longer supported.

Features

- Conforms with AS2 1.1 specification
- Can run as a server daemon
- Support for remote control
- Configurable Signature and encrytion
- Supports compression
- Configurable Synchronous and Asynchronous MDN
- Supports HTTPS transport protocol
- Supports filename preservation
- Supports FDA Automatic Submissions Gateway using custom headers
- Supports easy extending and adding of new modules via XML configuration
- Health check to run self tests of configured modules
- Support for load balancer configuration health checks

Code base deployed to Maven Central

Set Up OpenAS2

First, you need to install OpenAS2 on your machine.

Installation

You just need to download and extract the ZIP file for the installation. Once it's extracted, you can start the AS2Server by executing the bin/start-openas2.sh file. Make sure scripts are executable.

Configure OpenAS2

- configure partnerships.xml file
- configure config/config.xml file for file polling configurations
- configure certificates and your keystore
- export your OpenAS2 station's certificate chain
- import your Partner's certificate to your OpenAS2 side trust store
- you are done with the OpenAS2 side configuration

```
Select C:\WINDOWS\system32\cmd.exe
                                                                                                                                                                 П
<u> 2021-09-01 09</u>:13:51.930 FINE XMLSession: Command processor is disabled ... ignoring: org.openas2.cmd.proce
 2021-09-01 09:13:51.932 FINE XMLSession: Loading processor modules...
 2021-09-01 09:13:51.972 FINE IOUtil: Created directory D:\open_as2\openAS2\bin\..\config\..\data\toAny
2021-09-01 09:13:51.972 FINE IOUtil: Created directory D:\open_as2\openAS2\bin\..\config\..\data\pendinginfoMDN3
2021-09-01 09:13:51.974 FINE IOUtil: Created directory D:\open_as2\openAS2\bin\..\config\..\data\pendingMDN3 2021-09-01 09:13:51.975 FINE IOUtil: Created directory D:\open_as2\openAS2\bin\..\config\..\data\toPartnerA
2021-09-01 09:13:51.976 FINE IOUtil: Created directory D:\open_as2\openAS2\bin\..\config\..\data\toPartnerB
2021-09-01 09:13:52.190 FINE XMLSession: Module is disabled ... ignoring: <module classname="org.openas2.processor.receiver.AS2ReceiverModule.https.enabled$" errordir="$properties.storageBaseDi
r$/inbox/error" errorformat="sender.as2_id, receiver.as2_id, headers.message-id" port="10443" protocol="https" ssl_keys
ore="%home%/ssl_certs.jks" ssl_keystore_password="testas2" ssl_protocol="TLS"/>
2021-09-01 09:13:52.201 FINE XMLSession: Module is disabled ... ignoring: <module classname="org.openas2.processor.rece:
ver.AS2MDNReceiverModule" enabled="$properties.module.AS2MDNReceiverModule.https.enabled$" port="10444" protocol="https
ssl_keystore="%home%/ssl_certs.jks" ssl_keystore_password="testas2" ssl_protocol="TLS"/>
2021-09-01 09:13:52.206 FINE XMLSession: Module is disabled ... ignoring: <module classname="org.openas2.processor.receiver.HealthCheckModule" enabled="$properties.module.HealthCheckModule.enabled$" port="10099"/>
2021-09-01 09:13:52.329 FINE OpenAS2Server: Shutdown hook registered.
2021-09-01 09:13:52.330 FINE OpenAS2Server: Starting OpenAS2 Server v2.11.0...
2021-09-01 09:13:52.333 FINE DefaultProcessor: AS2DirectoryPollingModule started.
2021-09-01 09:13:52.337 FINE DefaultProcessor: AS2DirectoryPollingModule started.
2021-09-01 09:13:52.389 FINE DefaultProcessor: AS2DirectoryPollingModule started.
2021-09-01 09:13:52.608 FINE DefaultProcessor: DbTrackingModule started.
2021-09-01 09:13:52.621 FINE DefaultProcessor: AS2ReceiverModule started.
2021-09-01 09:13:52.622 FINE DefaultProcessor: AS2MDNReceiverModule started.
2021-09-01 09:13:52.624 FINE DefaultProcessor: DirectoryResenderModule started.
2021-09-01 09:13:52.626 FINE DefaultProcessor: 7 active module(s) started.
 2021-09-01 09:13:52.626 FINE IOUtil: Created directory D:\open_as2\openAS2\bin\..\config\..\data\resend 2021-09-01 09:13:52.627 FINE OpenAS2Server: OpenAS2 Server v2.11.0 started.
```

