Exp NO: 10 a

17/9/26

Aim:

To design and configure a simple internetwork using a router and two in cisco packet tracer and connectivity using PPU.

Step 1: configure Router1

1. open cisco packet tracer
2. Select Router → Router 1
3. open CLI and press enter
4. Enter
   enable
   config t
5. configure Fact ethernet 0/0:
   Interface fast ethernet 0/0
   IP address 192.168.10.1255.255.255.0
   No shut down.
6. configure Fast ethernet 0/0:
   Interface Fast ethernet 0/1
   IP address 192.168.101.255.255.255.0
   No Shutdown.

Step 2: configure PC0

Go to PC0 → desktop → IP configuration

IP address : 192.168.10.2

Subnet Mask : 255.255.255.0

Default Gateway : 192.168.10.1


Step 3: configure PC1

Go to PC1 → desktop → Ip Configuration.

Ipaddress : 192.168.20.2

Subnet mask : 255.255.2.55.0

Default Gateway: 198.168.20.1


Router0
Router1
PC0
PC1

Step 4: connect to devices

Use copper straight-Through cable.

Pc0 Fast Ethernet 0 → Router 1 Fast Ethernet 0/0

Pc1 Fast Ethernet 0 → Router 1 Fast Enternet 0/1

Step 5: Test Connectivity

1. Select simulation mode
2. choose Add Simple PDU
3. Click Pc0 → Pc1
4. If The PDU is Successful, the two network are communicating through the router.

Result:

The internetwork was Successfully designed and configured, and connectivity between Pc0 & Pc1 was verified.

Exp No: 10(b)
Date 19/9/16

Wireless Router, DHCP Server and Internet cloud.

Aim:

To design and configure and internetwork using a wireless router, DHCP servers and Internet clould and verify connectivity.

Step 1: Build the network

Add:

- Pc
- wireless router
- Laptop
- Cable Modem
- Internet cloud
- cisco.com server.

Step 2: connect Devices.

Use the appropriate cables

Pc → wireless router → cable modem

copper Straight – Through

wirless router → cable modem:

copper Straight - Through

cable modem → Internet cloud.

coaxial cable.

Internet cloud → cisco.com Server


copper Straight - Through.

Step 3: configure wireless router

1. open wireless Router → GUI
2. Go to wireless
3. Set DNS Server as 208.67.220.200.22
4. click Save Settings

Step 4:

configure cisco.com Server


Logical
Wireless Router
PC
Cable Modem
Internet
Cisco.com
Laptop
Realtime
Simulation

DHCP

DHCP : NO

Pool Name : DHCP Pool

default Gateway : 208.69.220.220

Starting IP : 208.69.220.1

Maximum Users : 50

click add

Step 5: Test connectivity

1. open PC → Desktop → command prompt
2. Type : ipconfig /release.
3. Then : ipconfig /renew
4. Test the Server : ping cisco.com

Result:

The wireless Internetwork was Successfully designed using a wireless router DHCP server and internet cloud. and connectivity was verified using ping command.