








```

Building configuration...

Current configuration : 100 bytes
!
interface Ethernet0/1
 ip address 1.0.0.1 255.0.0.0
 ip helper-address 12.0.0.2
 duplex auto
end

```



```

Current configuration : 107 bytes
!
interface Ethernet0/1
 ip address 212.25.0.1 255.255.255.0
 ip helper-address 12.0.0.2
 duplex auto
end

```

```
QEMU (Win-4)
C:\WINDOWS\system32\cmd.exe
Ethernet adapter Local Area Connection:

    Connection-specific DNS Suffix  . : 
    IP Address. . . . . : 212.25.0.51
    Subnet Mask . . . . . : 255.255.255.0
    Default Gateway . . . . . : 

C:\Documents and Settings\user>ipconfig

Windows IP Configuration

Ethernet adapter Local Area Connection:

    Connection-specific DNS Suffix  . : 
    IP Address. . . . . : 212.25.0.51
    Subnet Mask . . . . . : 255.255.255.0
    Default Gateway . . . . . : 212.25.0.1

C:\Documents and Settings\user>
```

```
Current configuration : 105 bytes
interface Ethernet0/1
 ip address 129.23.0.1 255.255.0.0
 ip helper-address 12.0.0.2
 duplex auto
```

```
QEMU (Win-3)
C:\WINDOWS\system32\cmd.exe
C:\Documents and Settings\user>ipconfig

Windows IP Configuration

Ethernet adapter Local Area Connection:

    Connection-specific DNS Suffix  . : 
    IP Address. . . . . : 129.23.0.51
    Subnet Mask . . . . . : 255.255.0.0
    Default Gateway . . . . . : 

C:\Documents and Settings\user>ipconfig

Windows IP Configuration

Ethernet adapter Local Area Connection:

    Connection-specific DNS Suffix  . : 
    IP Address. . . . . : 129.23.0.51
    Subnet Mask . . . . . : 255.255.0.0
    Default Gateway . . . . . : 129.23.0.1

C:\Documents and Settings\user>ipconfig
```