Proto:Game Boy Camera

> **This page details one or more prototype versions of *Game Boy Camera*.**

For the unreleased *Hello Kitty* edition of the game, see *Hello Kitty Pocket Camera*



This page is rather stubbly and could use some expansion.
Are you a bad enough dude to rescue this article (https://tcrf.net/index.php?title=Proto:Game_Boy_Camera&action=edit)?
Notes: Describe the rest of the functionality of the cart

Debagame Tester: Second Impact is a cartridge used for testing the *Game Boy Camera* hardware. "Debagame" means "peeping tom". and is also likely a pun on "debug".



Sommaire

Functionality
- SRAM TEST
- BANK TEST
- PROTECT TEST
- MOVIE TEST
- GALLERY
- COM

Unused Graphics

Source Code
- First Big Chunk
- Second Big Chunk

Functionality



To do:
A lot of this stuff still needs researched.


There are six options in the main menu.




SRAM TEST



- **VERIFY**
- **WRITE**
- **AGING**
  - **DECREMENT**
  - **00,00,FF,FF**
  - **55,55,AA,AA**
  - **ALL 00**
  - **ALL FF**
- **DUMP**: Press **Left/Right** to change the displayed bank from **00** through **0F**. Press **Up/Down** to scroll the selected bank.



AGING



DUMP

BANK TEST



PROTECT TEST



This needs some investigation.
Discuss ideas and findings on the talk page.
Specifically: What is this protecting? It doesn't seem to be the photo data...

- **PROTECT**: Displays current "protect" status, either "OK" or "NG" (no good).
- **ON**: Turn protect status ON.
- **OFF**: Turn protect status OFF.



MOVIE TEST

This is the mode for taking photos.



Controls:

- **A**: Snap and save photo. You can choose which slot to save the photo to, from 00 to 29.
- **B**: Cancel/return.
- **Left/Right**: Adjust offset, **01** through **83**.
- **Select**: Change trick lens modes, **00** through **1F**.
- **Start**: Open settings screen.



Settings options:

- **ディザ** (Dither): Set the dithering strength from 1 to 11, or OFF.
- **MODE**: Set camera mode.
  - **二次元エッジ強調** (2D edge emphasis): With GAIN levels 04H, 08H, and 00H.
  - **二次元エッジ** (2D edge)
  - **負画像** (Inverted)
  - **横エッジ強調** (Horizontal edge emphasis)
  - **縦エッジ強調** (Vertical edge emphasis)
- **EDGE**: Set 50%, 75%, 100%, 125%, 200%, 300%, 400%, or 500%.
- **パレット** (Palette): Set color palette order from 0 to 5.


The following settings are for reference and cannot be selected:

- **VREF**: Always set to 1.5V.
- **ゼロ点** (Zero point): Generally set to 負画像ゼロ点補正 (inverted image zero point compensation), but will change to 無し (none) in 二次元エッジ (2D edge) MODE.
- **GAIN**: Generally set to 04H, but can change to 08H or 00H in certain 二次元エッジ強調 (2D edge emphasis) MODEs.
- **オフセット** (Offset)
- **CHG**


Examples of different MODE settings




二次元エッジ強調 (00H)
2D edge emphasis (00H)



二次元エッジ強調 (04H)
2D edge emphasis (04H)



二次元エッジ強調 (08H)
2D edge emphasis (08H)




二次元エッジ
2D edge



負画像
Inverted



横エッジ強調
Horizontal edge emphasis



縦エッジ強調
Vertical edge emphasis

(Example photos: Chris Graves)


GALLERY

A basic photo gallery viewer. Press **Up/Down** to scroll through photos 00 through 29. Photos cannot be deleted; they can simply be overwritten with new ones from the MOVIE TEST mode.




COM


A basic Link Cable communication test. When two Testers are connected on this screen, pressing **A** on either Game Boy will cause the number to quickly "count" from **00** through **FF** in a loop on both screens.




Unused Graphics



Fourteen full-size pictures are found throughout the ROM data. Ten of them are photos of Nintendo employee Kentaro Nishimura, who is credited in the final game as coordinator and sound composer. The last four are drawings of a face which appear in the final game, though they're slightly less refined here.



UI elements for some sort of editor.



An alternate, probably earlier, logo for the title screen. It reads "*Debagame Tester NEO*".



An arrow hanging from a string. Probably an earlier menu cursor graphic, before it was replaced with the spinning face.

Source Code



To do:
Other bits?

Large chunks of commented source code are also found throughout the ROM. The two largest chunks are as follows:

First Big Chunk

```
        LD      (AKARUSA),A             ;目標値をワークに

        LD      A,$00
        LD      ($4000),A               ;ＲＡＭバンクの変更


;-------------現在のチャージタイムの表示---------------

        IFE     00E

        LD      A,(B_CNTR2)
        LD      (TEST1),A
        LD      A,(B_CNTR3)
        LD      (TEST2),A

        ENDIF

;-------------黒点数え（真ん中）-----------------------
        IFE     ZENTAI
        LD      BC,$00          ;真ん中8×7キャラの１の数を数える
                                ; 市松模様（448バイトをチェック）
        LD      de,BUF_ADR+$340
        CALL    LINE_CHECK
        LD      de,BUF_ADR+$440
        CALL    LINE_CHECK
        LD      de,BUF_ADR+$540
        CALL    LINE_CHECK
        LD      de,BUF_ADR+$640
        CALL    LINE_CHECK
        LD      de,BUF_ADR+$740
```

Second Big Chunk

```
AA, $AA, $AA, $AA, $AA, $AA, $AA

        DEFB    $AA, $AA, $AA, $B6, $1D, $A0, $A0, $A0, $A0
        DEFB    $A0, $A0, $A0, $A0, $A0, $A0, $A0, $1F
        DEFB    $AA, $AA, $AA, $AA, $AA, $AA, $AA, $AA
        DEFB    $AA, $AA, $AA, $AA, $AA, $AA, $AA

        DEFB    $AA, $AA, $AA, $AA, $1D, $A0, $A0, $A0, $A0
        DEFB    $A0, $A0, $A0, $A0, $[NUL]タ[?]ツA0, $A0, $1F
        DEFB    $AA, $AA, $AA, $AA, $AA, $AA, $AA, $AA
        DEFB    $AA, $AA, $AA, $AA, $AA, $AA, $AA

        DEFB    $AA, $AA, $AA, $AA, $1D, $A0, $A0, $A0, $A0
        DEFB    $A0, $A0, $A0, $A0, $A0, $A0, $A0, $1F
        DEFB    $AA, $AA, $AA, $AA, $AA, $AA, $AA, $AA
        DEFB    $AA, $AA, $AA, $AA, $AA, $AA, $AA

        DEFB04
        DB      $59, $70, $87, $03, $03, $04
        DB      $5A, $70, $86, $03, $03, $04
        DB      $5B, $70, $85, $03, $03, $04
        DB      $5C, $70, $84, $03, $03, $04
        DB      $5D, $70, $83, $03, $03, $04
        DB      $5E, $70, $82, $03, $03, $04
        DB      $5F, $70, $81, $03, $03, $04
        DB      $60, $70, $80, $02, $02, $03
        DB      $61, $70, $7F, $02, $02, $03
        DB      $62, $70, $7E, $02, $02, $03
        DB      $63, $70, $7D, $02, $02, $03
```


BIOS/Firmware ROMs **[masquer]**

Nintendo

Consoles	GameCube • Wii (Prototype) • Wii U • Switch (Prototype) • Switch 2 FamicomBox • Demo Vision • NES Classic Edition • SNES Classic Edition
Handhelds	Game Boy • Game Boy Color • Game Boy Advance (Prototype) • DS (Prototypes) • DSi (Prototypes) • 3DS (Prototype) • Game & Watch: Super Mario Bros.
Official Accessories	Family BASIC (Prototype) • Famicom Disk System • Study Box • Super Disc • Workboy • Super Game Boy • BS-X • XBAND (SNES) • Game Boy Camera (Prototype, Hello Kitty Pocket Camera) • GB Memory • Wideboy64 CGB • 64DD • Mobile Trainer • e-Reader • Game Boy Player
Unofficial Accessories	Game Genie (Game Boy) • Pro Action Replay (NES) • Game Saver+ • Game Genie (SNES) • Pro Action Replay (SNES) (MK2, MK3) • Action Replay (GameCube) • GameShark (Nintendo 64) • GB Hunter • Tri-Star • Mega Memory Card (Game Boy) • CodeBreaker (Game Boy Advance) • Action Replay DS • Action Replay DSi
Arcade Systems	Triforce

Sega

Consoles	Master System (Prototypes) • Genesis • Sega CD (Prototype) • 32X • Saturn • Dreamcast (Prototype) Genesis Mini • Genesis Mini 2

Accessories	Sega Graphic Board v2.0 • Game Genie (Genesis) • Game Genie (Game Gear) • Sega Channel (US) (Prototypes) • Visual Memory Unit
Arcade Systems	Sega Titan Video • Sega Hikaru • Triforce
	SNK
Consoles	Neo Geo • Neo Geo CD
Arcade Systems	Neo Geo • Hyper Neo Geo 64
	Sony
Consoles	PlayStation • PlayStation 2 • PlayStation 3 (Prototypes) • PlayStation 4 (Prototypes) • PlayStation 5 (Prototypes) PlayStation Classic
Handhelds	PlayStation Portable (Prototypes) • PlayStation Vita (Prototypes)
Unofficial Accessories	Xploder CD9000 Version 4.0 • Memory Manager Plus
	Microsoft
Consoles	Xbox (Prototypes) • Xbox 360 (Prototypes) • Xbox One (Prototypes) • Xbox Series X and S
	Others
3DO	3DO
Atari	Atari Flashback • Atari Flashback 2 • Atari Flashback 5 • Atari Gamestation Pro
Bandai	WonderSwan Color
Bit Corporation	Gamate
Brezzasoft	Crystal System
Commodore	Amiga CD32
GamePark	GP32
International Games System	PolyGame Master
JungleTac	Vii • Zone 60 • Wireless 60
Konami	Bubble System • System 573 TurboGrafx-16 Mini
LeapFrog	Leapster • Leapster2 • Didj • LeapPad Explorer • Epic • LeapTV
Nabi	Nabi SE
Namco	NA-1 and NA-2 • Triforce
NEC/Hudson	TurboGrafx-CD • United Amusements PC Engine
Philips	CD-i
retroUSB	AVS
Sammy	Atomiswave
TimeTop	GameKing
Tsukuda Original	Othello Multivision
VTech	V.Smile • V.Smile Baby

See Also

Handheld • Mini Console • Plug & Play • Specialized Console

Récupérée de « https://tcrf.net/index.php?title=Proto:Game_Boy_Camera&oldid=1982808 »

La dernière modification de cette page a été faite le 4 décembre 2025 à 06:07.

Le contenu est disponible sous licence Attribution 3.0 Unported sauf mention contraire.