

TOAnimate

GHOST RIG GUIDE



Bringing your asset into Blender

Link

Go to **File** > **Link...** > find the asset folder > ***Assetname*_Rig.blend** > **Collection** > ***Assetname*** > **Link** > select the armature > **Object** > **Library Override** > **Make**

Append


Go to **File** > **Append** > find the asset folder > ***Assetname*_Rig.blend** > **Collection** > ***Assetname*** > **Append**

TIP: Make sure that you move the assets in **Pose Mode** so that the functionality doesn't break.



Textures

In order for textures to be visible in Viewport shading, make sure to select “**Texture**” under the **Color** section.




RIG UI

Some more complex TOAnimate assets have a UI that you can access in the viewport's side menu after installing the add-on. The UI allows you to hide/reveal sets of controllers to make your rig view less cluttered, and also gives you access to custom properties, if the rig has any (will be listed below in this PDF guide). Select the **rig** > **Pose Mode** > press **N** to open N-menu > **RigUI** tab.

Add-on installation:

Go to **Edit** > **Preferences** > **Add-ons** > **Install**. Locate the downloaded add-on on your computer and select it (*don't unzip the file*). The '**TO Rig UI**' will now appear in the side menu of the viewport after pressing **N** (this only needs to be done once and works for any rig you purchase from the TOAnimate Store).

Periodically check for any updates to the add-on by clicking on the “**Check for Add-on Update**” button.



SPECIAL RIG PROPERTIES

1. God ctrl

Toggle subdivision:

Toggle to get a smoother looking model (slows down performance).

2. Arm Settings (gear ctrl)

IK/FK switch

Switch between IK and FK - arm/hand controllers will automatically swap as well.


1 = FK, 0 = IK

IK/FK snapping

In order for the transition between IK and FK to be seamless, use the **IK/FK snapping options**. The magnet will match the position of the controller on the specific frame (great for switching between IK and FK over 1 frame). The Action button will snap the position of the controller on all frames of the action.




How to use: When going from FK to IK, snap the IK controller's position to FK using the IK -> FK button, then slide the IK -> FK Switch slider to 0 (and vice versa).



Parent Spaces

Choose the appropriate space for the IK arm/pole parent from the drop-down menu and the controller will switch while maintaining its correct position in space (use the arrow on the right to switch all timeline keyframes at the same time).



FK Limb Follow

When set to 0, FK arms rotate with the body. When set to 1, arms maintain world orientation.


IK Stretch

Allows the arm geo to stretch to a certain distance.

3. Fingers

Finger Curve

Smooths out finger curves for a more polished look.




4. Elbow Tweak

Rubber Tweak


Rounds off the elbow for a more rubber hose look.

**Note that the "Arm Tweak" layer has to be activated to see these controllers.*



Elbow Stick

Sticks the elbow to the tweaker.



SHARE YOUR ANIMATIONS WITH US ON SOCIAL MEDIA!

- X: [@TOAnimate_](#)
- Instagram: [@toanimate.ca](#)
- LinkedIn: [@TOAnimate](#)



Thank you for your support!

TOAnimate
— Academy —