


Q-Assign IP addresses to all router interfaces in your Packet Tracer network and verify connectivity using the ping command.



Router 0

```
Router>enable
Router#
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface Serial0/1
Router(config-if)#ip address 10.0.0.2 255.0.0.0
Router(config-if)#no shutdown
Router(config-if)#
Router(config-if)#exit
Router(config)#interface Serial0/0
Router(config-if)#ip address 30.0.0.1 255.0.0.0
Router(config-if)#no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface Serial0/1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/1, changed state to up

%LINK-5-CHANGED: Interface Serial0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0, changed state to up

Router(config-if)#exit
Router(config)#show ip in
Router(config)#show ip interface brief
^
% Invalid input detected at '^' marker.

Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#show ip
Router#show ip in
Router#show ip interface brief
Interface                IP-Address      OK? Method Status          Protocol
FastEthernet0/0          unassigned      YES unset  administratively down down
FastEthernet0/1          unassigned      YES unset  administratively down down
Serial0/0                 30.0.0.1        YES manual up                up
Serial0/1                10.0.0.2        YES manual up                up
Router#ping 10.0.0.1

Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 10.0.0.1, timeout is 2 seconds:
!!!!
Success rate is 100 percent (5/5), round-trip min/avg/max = 1/5/21 ms

Router#
```

Router 1

```
Router>enable
Router#
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface Serial0/1
Router(config-if)#ip address 10.0.0.1 255.0.0.0
Router(config-if)#no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface Serial0/1, changed state to up

Router(config-if)#exit
Router(config)#interface Serial0/0
Router(config-if)#
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/1, changed state to up
ip address 20.0.0.1 255.0.0.0
Router(config-if)#no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface Serial0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0, changed state to up

Router(config-if)#exit
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#show ip interface brief
Interface          IP-Address      OK? Method Status          Protocol
FastEthernet0/0    unassigned      YES unset  administratively down down
FastEthernet0/1    unassigned      YES unset  administratively down down
Serial0/0          20.0.0.1        YES manual up             up
Serial0/1          10.0.0.1        YES manual up             up
Router#ping 30.0.0.2

Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 30.0.0.2, timeout is 2 seconds:
.....
Success rate is 0 percent (0/5)

Router#ping 20.0.0.2

Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 20.0.0.2, timeout is 2 seconds:
!!!!!!
Success rate is 100 percent (5/5), round-trip min/avg/max = 1/4/12 ms

Router#
```

Router 2

```
Router>enable
Router#
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface Serial0/0
Router(config-if)#ip address 30.0.0.2 255.0.0.0
Router(config-if)#no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface Serial0/0, changed state to up

Router(config-if)#exit
Router(config)#interface Serial0/1
Router(config-if)#ip address 20.0.0.2 255.0.0.0
Router(config-if)#no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface Serial0/1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/1, changed state to up

Router(config-if)#exit
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#show ip interface brief
Interface          IP-Address      OK? Method Status          Protocol
FastEthernet0/0    unassigned      YES unset  administratively down down
FastEthernet0/1    unassigned      YES unset  administratively down down
Serial0/0          30.0.0.2        YES manual up             up
Serial0/1          20.0.0.2        YES manual up             up
Router#ping 30.0.0.1

Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 30.0.0.1, timeout is 2 seconds:
!!!!!!
Success rate is 100 percent (5/5), round-trip min/avg/max = 1/4/17 ms

Router#
```