

```

// main.cpp

#define POLL_INTERVAL_MS 5000
#define REFRESH_INT_MS 30000

#include "box_actions.h"
#include "interop_comms.h"
#include <.common/comm.h>
#include <Arduino.h>
#include <SoftwareSerial.h>

unsigned long last_poll = 0;
unsigned long last_refresh = 0;

unsigned long time = 0;
// const int SENSOR_READ_DELAY = 100;

const int status_pins[] = {Pins::FRESH_PIN, Pins::GOING_BAD_PIN, Pins::EXPIRED_PIN};

int DetermineFoodStatus();
void UpdateStatusDisplay(int Cond);

SoftwareSerial nodemcu(5, 6);

void setup()
{
    d_SerialBegin(9600);

    RadioSetup();

    pinMode(Pins::FRESH_PIN, OUTPUT);
    pinMode(Pins::GOING_BAD_PIN, OUTPUT);
    pinMode(Pins::EXPIRED_PIN, OUTPUT);

    pinMode(Pins::ALC_SENSOR_PIN, INPUT);
    pinMode(Pins::CH3_SENSOR_PIN, INPUT);

    digitalWrite(Pins::FRESH_PIN, HIGH);
    delay(1000);
    digitalWrite(Pins::FRESH_PIN, LOW);
    delay(1000);
    digitalWrite(Pins::GOING_BAD_PIN, HIGH);
    delay(1000);
    digitalWrite(Pins::GOING_BAD_PIN, LOW);
    delay(1000);
    digitalWrite(Pins::EXPIRED_PIN, HIGH);
    delay(1000);
    digitalWrite(Pins::EXPIRED_PIN, LOW);

    d_SerialPrintln("SFES Main Indicator Init'sed");

    nodemcu.begin(9600);

```

```

char response[120];

d_SerialPrintln("Entering Setup, sending Active Boxes request.");
if (NodeMCUTransmit(Requests::ActiveBoxes, &nodemcu, NULL, response,
sizeof(response)))
{
    d_SerialPrint("Receieved input:");
    d_SerialPrintlnV(response);
    ParseBoxes(response);
}
else
{
    d_SerialPrintln("Failed to get active boxes");
}
}

void loop()
{
    unsigned long now = millis();

    if (now - last_poll >= POLL_INTERVAL_MS)
    {
        d_SerialPrintln("Polling...");
        last_poll = now;
        Poller();
        NodeMcuUpdate(&nodemcu);
    }
    if (now - last_refresh >= REFRESH_INT_MS)
    {
        d_SerialPrintln("Refreshing...");
        last_refresh = now;
        char response[120];

        if (NodeMCUTransmit(Requests::ActiveBoxes, &nodemcu, NULL, response,
sizeof(response)))
        {
            d_SerialPrint("Receieved input:");
            d_SerialPrintlnV(response);
            ParseBoxes(response);
        }
        else
        {
            d_SerialPrintln("Failed to get active boxes");
        }
    }
}

```