LoopScribe

One-page summary based on repo evidence

Repo basis: README.md, pyproject.toml, src/recorder_app/*.py

WHAT IT IS

LoopScribe is a local Windows desktop app that records system audio with WASAPI loopback or imports existing audio files and transcribes them with faster-whisper. It stores recordings and transcripts on disk and exposes the workflow through a PySide6 GUI with hotkeys.

WHO IT IS FOR

Primary persona: a Windows user who needs quick local transcription for played audio, meetings, calls, or saved audio files.

WHAT IT DOES

- Records Windows system audio through WASAPI loopback.
- Supports microphone-only and combined system-audio-plus-microphone capture.
- Offers global start and stop hotkeys plus push-to-transcribe.
- Imports .wav, .mp3, .m4a, .flac, .ogg, and .aac audio files.
- Runs local faster-whisper transcription with selectable language, model, and performance profile.
- Shows transcription progress and an editable transcript, with clipboard copy support.
- Auto-saves transcript files and exports to .txt, .srt, or .vtt.

REPO NOTES

- Remote backend/API: Not found in repo.
- Database/auth service: Not found in repo.
- First transcription downloads the selected Whisper model.

HOW IT WORKS

Compact architecture and data flow:

UI + settings

PySide6 MainWindow loads SettingsStore, builds the desktop UI, and wires buttons and hotkeys.

↓

Capture

AudioCaptureService records to WAV via soundcard and soundfile using WASAPI loopback, microphone, or both.

↓

Transcribe

TranscriptionWorker runs FastTranscriptionService, which calls faster-whisper locally and caches models.

↓

Outputs

Transcript text is saved under transcripts/, shown in the editor, then copied to clipboard or exported.

Observed flow: hotkey/button -> WAV/import -> local transcription -> transcript/export.

HOW TO RUN

Minimal getting-started path:

1. Windows 10/11 and Python 3.10+.
2. python -m venv .venv
3. .venv\Scripts\Activate.ps1
4. python -m pip install -e .
5. python -m recorder_app.main or start.bat