Basic Character Animations

Free & Complete Edition — Documentation & Setup Guide

A collection of Humanoid character animations for Unity projects, available in both In-Place and Root Motion versions.

Table of Contents

1.	**Introduction**
2.	Package Overview
3.	Free Edition
4.	Complete Edition
5.	Requirements & Compatibility
6.	Installing the Package
7.	Using the Animations
8.	Humanoid Retargeting
9.	In-Place Animations
10.	Root Motion Animations
11.	Animation Categories
12.	Recommended Workflow
13.	Troubleshooting
14.	Support

1. Introduction

Basic Character Animations is an animation package designed for Unity projects. It provides common character actions, locomotion, and traversal animations suitable for character-based gameplay systems.

The package is available in two editions: **Basic Character Animations – Free** and **Basic Character Animations – Complete**. The Complete edition contains all animations from the Free edition plus additional movement and traversal animations.

All animation sets are provided in both **In-Place** and **Root Motion** versions.

2. Package Overview

Feature	Free Edition	Complete Edition
3D Character	Included	Included
Rig	Humanoid	Humanoid
Retargeting	Supported	Supported
In-Place Versions	Included	Included
Root Motion Versions	Included	Included
Rendering Pipeline	Built-in / URP / HDRP	Built-in / URP / HDRP

3. Free Edition

Basic Character Animations – Free contains 28 base animations. Each is available in both In-Place and Root Motion versions, resulting in **56 animation clips** in total.

Category	Animations	Base Clips
Idle	2 Idle animations	2
Emote	2 Emote animations	2
Crouch	Idle, Walk Forward	2
Walk	8-Way Walk	8
Run	8-Way Run	8
Swim	Idle, Swim Forward	2
Run & Climb	Run & Climb	1
Jump	Start, Loop, End	3
Total		28

4. Complete Edition

Basic Character Animations – Complete contains all Free edition content plus 18 additional base animations. With both In-Place and Root Motion versions, the Complete edition contains **92 animation clips** in total.

Category	Animations	Base Clips
Free Edition	All Free edition animations	28

Category	Animations	Base Clips
Push & Pull	Idle, Push Forward, Push Backward	3
Slide	3 Slide animations	3
Roll	Roll	1
Wall Climb	8-Way Wall Climb	8
Ladder Climb	3 Ladder Climb animations	3
Total		46

5. Requirements & Compatibility

The package is animation-focused and can be used with the **Built-in Render Pipeline**, **Universal Render Pipeline (URP)**, or **High Definition Render Pipeline (HDRP)**.

The included character and animation content use Unity's **Humanoid** animation system. Compatible user-created Humanoid characters can retarget the animations through Unity's Avatar workflow.

6. Installing the Package

Step 1 — Import the package
Import the selected edition into your Unity project using Unity's standard package import workflow.

Step 2 — Locate the assets
Locate the included character model and animation files.

Step 3 — Configure your character
If using your own character, configure its model as Humanoid and create or assign the appropriate Avatar.

Step 4 — Add the clips
Add the required clips to your Animator Controller and create the states and transitions required by your project.

7. Using the Animations

The animation clips are reusable assets and can be integrated into a custom Animator Controller or another Unity-supported animation workflow.

Choose the **In-Place** version when movement is controlled separately by your character controller. Choose the **Root Motion** version when the animation is intended to drive character movement.

8. Humanoid Retargeting

The animations are authored for Unity's Humanoid animation system. Users can retarget the clips to their own compatible Humanoid characters.

Basic retargeting workflow:
1. Import your character.
2. Select the character model.
3. Open the Rig import settings.
4. Set Animation Type to **Humanoid**.
5. Configure or create the Avatar if required.
6. Apply the import settings.

7. Use the clips in your Animator Controller.

Retargeting quality can depend on the target character's bone structure and Avatar configuration. Make sure the target character has a valid Humanoid Avatar.

9. In-Place Animations

In-Place animations are designed for projects where character movement is controlled independently from the animation. The character remains in place while the animation provides the visual movement.

10. Root Motion Animations

Root Motion animations contain movement information intended to be applied to the character through Unity's Animator.

Basic Root Motion setup:
1. Add the Root Motion clip to your Animator Controller.
2. Select the character's Animator component.
3. Enable **Apply Root Motion** when your controller is designed to use Animator-driven movement.
4. Test the animation and adjust your controller as required.

If your character controller already controls movement independently, use the In-Place version unless your controller is specifically designed to work with Root Motion.

11. Animation Categories

Category	Included Content
Idle	Basic idle animations.
Emote	Basic character emote animations.
Walk	8-Way walking locomotion.
Run	8-Way running locomotion.
Crouch	Crouch Idle and Crouch Walk Forward.
Swim	Swim Idle and Swim Forward.
Jump	Jump Start, Loop, and End.
Run & Climb	Run & Climb movement.
Push & Pull	Idle, Push Forward, and Push Backward. Complete edition.
Slide	Three sliding animations. Complete edition.
Roll	Roll animation. Complete edition.
Wall Climb	8-Way wall climbing. Complete edition.
Ladder Climb	Three ladder climbing animations. Complete edition.

12. Recommended Workflow

1. Import the desired edition.
2. Configure your character as Humanoid.

3. Verify that the Humanoid Avatar is valid.
4. Decide whether your project uses In-Place or Root Motion movement.
5. Add the appropriate clips to your Animator Controller.
6. Configure Animator states and transitions.
7. Test the animations with your character.

13. Troubleshooting

Animation does not play correctly
Check that the animation is assigned to the correct Animator state and that the character has a valid Humanoid Avatar.

Character appears in a T-pose
Check the model's Rig settings and make sure Animation Type is set to Humanoid and the Avatar is valid.

Root Motion does not move the character
Make sure you are using the Root Motion version and that **Apply Root Motion** is enabled when your controller is intended to use Animator-driven movement.

Animation looks incorrect on a custom character
Verify the target character's Humanoid Avatar and bone mapping before troubleshooting the animation itself.

14. Support

Thank you for using **Basic Character Animations**. If you encounter an issue not covered in this documentation, please refer to the support information provided with the Unity Asset Store package.